Package 'factorstochvol'

December 7, 2021

Encoding UTF-8

Type Package

Title Bayesian Estimation of (Sparse) Latent Factor Stochastic Volatility Models

Version 1.0.1

Description Markov chain Monte Carlo (MCMC) sampler for fully Bayesian estimation of latent factor stochastic volatility models with interweaving <doi:10.1080/10618600.2017.1322091>. Sparsity can be achieved through the usage of Normal-Gamma priors on the factor loading matrix <doi:10.1016/j.jeconom.2018.11.007>.

License GPL (>= 2)

Depends R (>= 3.0.2)

- **Imports** GIGrvg (>= 0.4), Rcpp (>= 1.0.0), corrplot, methods, grDevices, graphics, stats, utils, stochvol (>= 3.0.2)
- **Suggests** LSD (>= 4.0-0), coda (>= 0.19-2), knitr, RColorBrewer, testthat (>= 2.1.0), zoo

LinkingTo Rcpp, RcppArmadillo (>= 0.9.900), stochvol

RoxygenNote 7.1.2

BuildResaveData best

VignetteBuilder knitr

NeedsCompilation yes

Author Gregor Kastner [aut, cre] (<https://orcid.org/0000-0002-8237-8271>), Darjus Hosszejni [ctb] (<https://orcid.org/0000-0002-3803-691X>), Luis Gruber [ctb] (<https://orcid.org/0000-0002-2399-738X>)

Maintainer Gregor Kastner <gregor.kastner@aau.at>

Repository CRAN

Date/Publication 2021-12-07 09:00:02 UTC

R topics documented:

factorstochvol-package	3
comtimeplot	5
corelement	6
corimageplot	6
cormat	8
cormat.fsvdraws	8
cormat.fsvsim	9
corplot	10
cortimeplot	11
covelement	12
covmat	13
covmat.fsvdraws	13
covmat.fsvsim	15
evdiag	15
expweightcov	16
facloadcredplot	17
facloaddensplot	17
facloadpairplot	18
facloadpointplot	19
facloadtraceplot	20
findrestrict	21
fsvsample	22
fsvsim	28
ledermann	
logret	
logvartimeplot	
orderident	
paratraceplot	
plot.fsvdraws	33
plotalot	34
predcond	35
predcor	
predcov	
predh	38
predloglik	39
predloglikWB	40
predprecWB	
preorder	43
print.fsvdraws	44
runningcormat	44
runningcovmat	45
signident	46
voltimeplot	47

factorstochvol-package

Bayesian Estimation of (Sparse) Latent Factor Stochastic Volatility Models through MCMC

Description

This packages provides a Markov chain Monte Carlo (MCMC) sampler for fully Bayesian estimation of latent factor stochastic volatility models. Sparsity can be achieved through the usage of Normal-Gamma priors on the factor loadings matrix.

Details

In recent years, multivariate factor stochastic volatility (SV) models have been increasingly used to analyze financial and economic time series because they can capture joint (co-)volatility dynamics by a small number of latent time-varying factors. The main advantage of such a model is its parsimony, as all variances and covariances of a time series vector are governed by a low-dimensional common factor with the components following independent SV models. For problems of this kind, MCMC is a very efficient estimation method, it is however associated with a considerable computational burden when the number of assets is moderate to large. To overcome this, the latent volatility states are drawn "all without a loop" (AWOL), ancillarity-sufficiency interweaving strategies (ASIS) are applied to sample the univariate components as well as the factor loadings. Thus, this package can be applied directly estimate time-varying covariance and correlation matrices for medium-and high-dimensional time series. To guarantee sparsity, a hierarchical Normal-Gamma prior can be used for the factor loadings matrix which shrinks the unnecessary factor loadings towards zero.

Note

This package is currently in active development; the interface of some of the functions might change. Moreover, even though I tried to carefully check everything, factorstochvol may still contain typos, inconsistencies, or even bugs. Your comments and suggestions are warmly welcome!

Author(s)

Gregor Kastner <gregor.kastner@wu.ac.at>

References

Kastner, G., Frühwirth-Schnatter, S., and Lopes, H.F. (2017). Efficient Bayesian Inference for Multivariate Factor Stochastic Volatility Models. *Journal of Computational and Graphical Statistics*, **26**(4), 905–917, doi: 10.1080/10618600.2017.1322091.

Kastner, G. (2019). Sparse Bayesian Time-Varying Covariance Estimation in Many Dimensions. *Journal of Econometrics*, **210**(1), 98–115. doi: 10.1016/j.jeconom.2018.11.007.

Kastner, G. and Frühwirth-Schnatter, S. (2014). Ancillarity-Sufficiency Interweaving Strategy (ASIS) for Boosting MCMC Estimation of Stochastic Volatility Models. *Computational Statistics and Data Analysis*, doi: 10.1016/j.csda.2013.01.002.

See Also

stochvol

Examples

```
set.seed(1)
# simulate data from a (small) factor SV model:
sim <- fsvsim(series = 5, factors = 2)</pre>
# estimate the model (CAVEAT: only few draws!)
res <- fsvsample(sim$y, factors = 2, draws = 2000, burnin = 500)</pre>
# plot implied volas overtime:
voltimeplot(res)
# plot correlation matrix at some points in time:
par(mfrow = c(2,2))
corimageplot(res, seq(1, nrow(sim$y), length.out = 4),
             fsvsimobj = sim, plotCI = 'circle',
             plotdatedist = -2)
# plot (certain) covariances and correlations over time
par(mfrow = c(2,1))
covtimeplot(res, 1)
cortimeplot(res, 1)
# plot (all) correlations over time
corplot(res, fsvsimobj = sim, these = 1:10)
# plot factor loadings
par(mfrow = c(1,1))
facloadpointplot(res, fsvsimobj = sim)
facloadpairplot(res)
facloadcredplot(res)
facloaddensplot(res, fsvsimobj = sim)
# plot latent log variances
logvartimeplot(res, fsvsimobj = sim, show = "fac")
logvartimeplot(res, fsvsimobj = sim, show = "idi")
# plot communalities over time
comtimeplot(res, fsvsimobj = sim, show = 'joint')
comtimeplot(res, fsvsimobj = sim, show = 'series')
```

4

comtimeplot

Description

comtimeplot plots the communalities over time, i.e. the series-specific percentage of variance explained through the common factors.

Usage

```
comtimeplot(
    x,
    fsvsimobj = NULL,
    show = "series",
    maxrows = 5,
    ylim = c(0, 100)
)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	Object of class 'fsvsim' (or NULL), usually resulting from a call to fsvsim. Defaults to NULL.
show	Indicator whether to show joint ('joint'), series-specific ('series'), or both ('both') communalities.
maxrows	Single positive integer denoting the maximum number of series in each plot. Defaults to 5.
ylim	Vector of length two denoting the range of the horizontal axis. Defaults to 1.

Details

This function displays the joint (average) communalities over time and all series-specific communalities. If communalities haven't been stored during sampling, comtimeplot produces an error.

Value

Returns x invisibly.

See Also

```
Other plotting: corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(),
paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot()
```

corelement

Description

corelement extracts the model-implied (time-varying) correlations between (exactly) two component series.

Usage

corelement(x, i, j, these = seq_len(nrow(x\$y)))

Arguments

х	Object of class 'fsvsim', usually resulting from a call of the function fsvsim.
i	Index of component series 1.
j	Index of component series 2.
these	Vector indicating which points in time should be extracted.

Value

Vector with the requested correlations.

See Also

Other simulation: cormat.fsvsim(), covelement(), covmat.fsvsim()

corimageplot

Plot correlation matrices for certain points in time

Description

corimageplot plots the model-implied correlation matrices for one or several points in time.

Usage

```
corimageplot(
    x,
    these = seq_len(nrow(x$y)),
    order = "original",
    these4order = these,
    plotdatedist = 0,
    plotCI = "n",
    date.cex = 1.5,
    col = NULL,
```

corimageplot

```
fsvsimobj = NULL,
plottype = "corrplot",
...
)
```

Arguments

x	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
these	Index vector containing the time points to plot. Defaults to $seq_len(nrow(x$y))$.
order	String, where 'none' and 'original' indicate not to mess with the series or- dering. Other keywords (e.g. 'hclust') will be forwarded to corrMatOrder.
these4order	Index vector containing the time points used for ordering. Probably, the default (these) is what you want.
plotdatedist	Numerical value indicating where the dates should be plotted.
plotCI	String. If not equal to 'n', posterior credible regions are added (posterior mean +/- 2 posterior sd). Ignored if plottype is "imageplot".
date.cex	Size multiplier for the dates.
col	Color palette or NULL (the default).
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
plottype	Indicates which type of plot should be drawn. Can be "corrplot" for corrplot (recommended for up to around 20 series), or "imageplot" for a simpler image plot.
	Additional parameters will be passed on to corrplot. Ignored if plottype is "imageplot".

Value

Returns x invisibly.

Note

If correlations haven't been stored during sampling, corimageplot produces an error.

See Also

```
Other plotting: comtimeplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(),
paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot()
```

cormat

Description

Generic function for extracting model-implied correlation matrices, either from the MCMC output, or from the simulated model. Details about the function's behavior can be found in cormat.fsvdraws (the function invoked when applied to MCMC output) or cormat.fsvsim (the function invoked when applied to a simulated model.

Usage

cormat(x, ...)

Arguments

Х	An object of class fsvdraws or fsvsim.
	Arguments to be passed to methods.

Value

Structure containing the model-implied covariance matrix.

See Also

```
Other generics: covmat()
```

cormat.fsvdraws Extract posterior draws of the model-implied correlation matrix

Description

cormat extracts draws from the model-implied correlation matrix from an fsvdraws object for all points in time which have been stored.

Usage

```
## S3 method for class 'fsvdraws'
cormat(x, timepoints = "all", ...)
```

Arguments

Х	Object of class 'fsvdraws', usually resulting from a call of fsvsample.
timepoints	Vector indicating at which point(s) in time (of those that have been stored during sampling) the correlation matrices should be extracted. Can also be "all" or "last".
	Ignored.

cormat.fsvsim

Value

Array of dimension m times m times draws times timepoints containing the posterior draws for the model-implied covariance matrix.

Note

Currently crudely implemented as a double loop in pure R, may be slow.

See Also

Other extractors: covmat.fsvdraws(), runningcormat(), runningcovmat()

Examples

```
set.seed(1)
sim <- fsvsim(n = 500, series = 3, factors = 1) # simulate</pre>
res <- fsvsample(sim$y, factors = 1, keeptime = "all") # estimate</pre>
cors <- cormat(res, "last") # extract</pre>
# Trace plot of determinant of posterior correlation matrix
# at time t = n = 500:
detdraws <- apply(cors[,,,1], 3, det)</pre>
ts.plot(detdraws)
abline(h = mean(detdraws), col = 2)
                                            # posterior mean
abline(h = median(detdraws), col = 4)
                                            # posterior median
abline(h = det(cormat(sim, "last")[,,1]), col = 3) # implied by DGP
# Trace plot of draws from posterior correlation of Sim1 and Sim2 at
# time t = n = 500:
ts.plot(cors[1,2,,1])
abline(h = cormat(sim, "last")[1,2,1], col = 3) # "true" value
# Smoothed kernel density estimate:
plot(density(cors[1,2,,1], adjust = 2))
# Summary statistics:
summary(cors[1,2,,1])
```

cormat.fsvsim	Extract "true" model-implied correlation matrix for several points in
	time

Description

cormat extracts the model-implied (time-varying) covariance matrix from an fsvsim object.

Usage

```
## S3 method for class 'fsvsim'
cormat(x, timepoints = "all", ...)
```

Arguments

х	Object of class 'fsvsim', usually resulting from a call of the function fsvsim.
timepoints	Vector indicating at which point(s) in time the correlation matrices should be extracted. Can also be "all" or "last".
	Ignored.

Value

Array of dimension m times m times length(timepoints), containing the model-implied correlation matrix.

Note

Currently crudely implemented as an R loop over all time points, may be slow.

See Also

Other simulation: corelement(), covelement(), covmat.fsvsim()

corplot

Plots pairwise correlations over time

Description

corplot gives an overview of (certain) pairwise correlations. Throws a warning if these haven't been stored during sampling.

Usage

```
corplot(
    x,
    fsvsimobj = NULL,
    these = 1:(ncol(x$y) * (ncol(x$y) - 1)/2),
    start = 1,
    end = nrow(x$y),
    maxrows = 10,
    ...
)
```

10

cortimeplot

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
these	Indicator which correlations should be plotted. Default is all.
start	First point in time to plot.
end	Last point in time to plot.
maxrows	The maximum number of rows per page.
	Other arguments will be passed on to ts.plot.

Value

Returns x invisibly.

See Also

```
Other plotting: comtimeplot(), cortimeplot(), evdiag(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(),
paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot()
```

cortimeplot *Plot correlations over time*.

Description

cortimeplot draws correlations over time.

Usage

```
cortimeplot(
    x,
    series,
    these = seq_len(nrow(x$y)),
    type = "cor",
    statistic = "mean"
)
covtimeplot(
    x,
    series,
    these = seq_len(nrow(x$y)),
    type = "cov",
    statistic = "mean"
)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
series	Single number, coercible to integer. Indicates the series relative to which corre- lations are drawn.
these	Index vector containing the time points to plot. Defaults to seq_len(nrow(x\$y)).
type	What to plot, usually "cor" or "cov".
statistic	Which posterior summary should be plotted, usually "mean".

Details

This function displays one component series' time-varying correlations with the other components series. Throws an error if correlations haven't been stored during sampling.

Value

Returns x invisibly.

See Also

```
Other plotting: comtimeplot(), corimageplot(), corplot(), evdiag(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(),
paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot()
```

covelement	Extract "true" model-implied covariances of two series only
------------	---

Description

covelement extracts the model-implied (time-varying) covariances between (exactly) two component series.

Usage

```
covelement(x, i, j, these = seq_len(nrow(x$y)))
```

Arguments

Х	Object of class 'fsvsim', usually resulting from a call of the function fsvsim.
i	Index of component series 1.
j	Index of component series 2.
these	Vector indicating which points in time should be extracted, defaults to all.

Value

Vector with the requested covariances.

covmat

See Also

Other simulation: corelement(), cormat.fsvsim(), covmat.fsvsim()

covmat

Generic extraction of covariance matrix

Description

Generic function for extracting model-implied covariance matrices, either from the MCMC output, or from the simulated model. Details about the function's behavior can be found in covmat.fsvdraws (the function invoked when applied to MCMC output) or covmat.fsvsim (the function invoked when applied to a simulated model.

Usage

covmat(x, ...)

Arguments

х	An object of class fsvdraws or fsvsim.
	Arguments to be passed to methods.

Value

Structure containing the model-implied covariance matrix.

See Also

Other generics: cormat()

covmat.fsvdraws Extract posterior draws of the model-implied covariance matrix

Description

covmat extracts draws from the model-implied covariance matrix from an fsvdraws object for all points in time which have been stored.

Usage

```
## S3 method for class 'fsvdraws'
covmat(x, timepoints = "all", ...)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call of fsvsample.
timepoints	Vector indicating at which point(s) in time (of those that have been stored during sampling) the correlation matrices should be extracted. Can also be "all" or "last".
	Ignored.

Value

Array of dimension m times m times draws times timepoints containing the posterior draws for the model-implied covariance matrix.

Note

Currently crudely implemented as a double loop in pure R, may be slow.

See Also

Other extractors: cormat.fsvdraws(), runningcormat(), runningcovmat()

Examples

```
set.seed(1)
sim <- fsvsim(n = 500, series = 3, factors = 1) # simulate</pre>
res <- fsvsample(sim$y, factors = 1, keeptime = "all") # estimate</pre>
covs <- covmat(res, "last") # extract</pre>
# Trace plot of determinant of posterior covariance matrix
# at time t = n = 500:
detdraws <- apply(covs[,,,1], 3, det)</pre>
ts.plot(detdraws)
abline(h = mean(detdraws), col = 2)  # posterior mean
abline(h = median(detdraws), col = 4)  # posterior median
abline(h = det(covmat(sim, "last")[,,1]), col = 3) # implied by DGP
# Trace plot of draws from posterior covariance of Sim1 and Sim2 at
# time t = n = 500:
ts.plot(covs[1,2,,1])
abline(h = covmat(sim, "last")[1,2,1], col = 3) # "true" value
# Smoothed kernel density estimate:
plot(density(covs[1,2,,1], adjust = 2))
# Summary statistics:
summary(covs[1,2,,1])
```

covmat.fsvsim

Description

covmat extracts the model-implied (time-varying) covariance matrix from an fsvsim object.

Usage

```
## S3 method for class 'fsvsim'
covmat(x, timepoints = "all", ...)
```

Arguments

х	Object of class 'fsvsim', usually resulting from a call of the function fsvsim.
timepoints	Vector indicating at which point(s) in time the correlation matrices should be extracted. Can also be "all" or "last".
	Ignored.

Value

Array of dimension m times m times length(timepoints), containing the model-implied covariance matrix.

Note

Currently crudely implemented as an R loop over all time points, may be slow.

See Also

Other simulation: corelement(), cormat.fsvsim(), covelement()

evdiag	Plots poste	ior draws	and	posterior	means	of	the	eigenvalues	of
	crossprod(fa	cload)							

Description

evdiag computes, returns, and visualizes the eigenvalues of crossprod(facload). This can be used as a rough guide to choose the numbers of factors in a model.

Usage

evdiag(x)

Arguments

Х

Object of class 'fsvdraws', usually resulting from a call to fsvsample.

Value

Invisibly returns a matrix with posterior samples of the eigenvalues of crossprod(facload)

Note

Experimental feature. Please be aware that - for the sake of simplicity and interpretability - both the time-varying idiosyncratic as well as the time-varying factor volatilities are simply ignored.

See Also

```
Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(),
paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot()
```

expweightcov

Computes the empirical exponentially weighted covariance matrix

Description

A common way to get estimates for time-varying covariance matrices is the compute the exponentially weighted empirical covariance matrix.

Usage

expweightcov(dat, alpha = 4/126, hist = 180)

Arguments

dat	Matrix containing the data, with n rows (points in time) and m columns (component series).
alpha	Speed of decay.
hist	How far to go back in time?

Value

A m times m covariance matrix estimate.

facloadcredplot Displays bivariate marginal posterior distribution of factor loadings.

Description

facloadcredplot illustrates the bivariate marginals of the factor loadings distribution. It is a monochrome variant of facloadpairplot.

Usage

```
facloadcredplot(x, quants = c(0.01, 0.99))
```

Arguments

Х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
quants	Posterior quantiles to be plotted.

Value

Returns x invisibly.

See Also

```
Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloaddensplot(),
facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(), paratraceplot(),
plot.fsvdraws(), plotalot(), voltimeplot()
```

facloaddensplot	Density plots of factor loadings draws

Description

facloaddensplot draws kernel smoothed density plots of the marginal factor loadings posterior.

Usage

```
facloaddensplot(x, fsvsimobj = NULL, rows = 5, thesecols = NULL, xlim = NULL)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
rows	Number of rows per page.
thesecols	Which factor loadings columns should be plotted? Defaults to 1:r.
xlim	Vector of length two containing lower and upper bounds of the horizontal axis. If NULL, these are automatically determined.

Value

Returns x invisibly.

See Also

```
Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(),
facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(), paratraceplot(),
plot.fsvdraws(), plotalot(), voltimeplot()
```

facloadpairplot Displays bivariate marginal posterior distributions of factor loadings.

Description

facloadpairplot illustrates the bivariate marginals of the factor loadings distribution. For a monochrome variant, see facloadcredplot.

Usage

```
facloadpairplot(x, maxpoints = 500, alpha = 20/maxpoints, cex = 3)
```

Arguments

Х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
maxpoints	The maximum amount of posterior draws to plot. If the number of draws stored in x exceeds this number, draws are thinned accordingly.
alpha	Level of transparency.
cex	Controls the size of the dots.

Value

Returns x invisibly.

See Also

Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(), facloaddensplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(), paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot()

18

facloadpointplot Displays point estimates of the factor loadings posterior.

Description

facloadpointplot illustrates point estimates (mean, median, ...) of the estimated factor loadings matrix.

Usage

```
facloadpointplot(
    x,
    fsvsimobj = NULL,
    statistic = "median",
    cex = 6.5,
    alpha = 0.2,
    allpairs = FALSE,
    col = NULL
)
```

Arguments

x	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
statistic	Character string indicating which posterior statistic should be displayed.
cex	Controls the size of the dots.
alpha	Controls the level of transparency.
allpairs	Logical value; if set to TRUE, all possible pairwise combinations will be plotted.
col	Vector of length m (number of component series), containing rgb-type color codes used for plotting. Will be recycled if necessary.

Value

Returns x invisibly, throws a warning if there aren't any factors to plot.

See Also

```
Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadtraceplot(), logvartimeplot(), paratraceplot(),
plot.fsvdraws(), plotalot(), voltimeplot()
```

facloadtraceplot Trace plots of factor loadings draws

Description

facloadtraceplot draws trace plots of the factor loadings. Can be an important tool to check MCMC convergence if inference about (certain) factor loadings sought.

Usage

```
facloadtraceplot(
    x,
    fsvsimobj = NULL,
    thinning = NULL,
    maxrows = 10,
    ylim = NULL
)
```

Arguments

x	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
thinning	Plot every thinningth draw.
maxrows	Indicates the maximum number of rows to be drawn per page.
ylim	Vector of length two containing lower and upper bounds of the vertical axis. If NULL, these are automatically determined.

Value

Returns x invisibly.

See Also

Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(), facloaddensplot(), facloadpairplot(), facloadpointplot(), logvartimeplot(), paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot() findrestrict

Description

In factor SV models, the identification of the factor loadings matrix is often chosen through a preliminary static factor analysis. After a maximum likelihood factor model is fit to the data, variables are ordered as follows: The variable with the lowest loadings on all factors except the first (relative to it) is determined to lead the first factor, the variable with the lowest loadings on all factors except the first two (relative to these) is determined to lead the second factor, etc.

Usage

```
findrestrict(dat, factors, transload = abs, relto = "all")
```

Arguments

dat	Matrix containing the data, with n rows (points in time) and m columns (component series).
factors	Number of factors to be used.
transload	Function for transforming the estimated factor loadings before ordering. Defaults to the absolute value function.
relto	Can be 'none', 'current' or 'all'. If 'none', the series with the highest loadings is placed first, the series with the second highest is placed second, and so on. If 'current', the current factor loading is used as a reference, if 'all', all previous loadings are summed up to be the reference.

Value

A m times factors matrix indicating the restrictions.

Note

This function is automatically invoked by fsvsample if restrict is set to 'auto'.

See Also

ledermann

fsvsample

Markov Chain Monte Carlo (MCMC) Sampling for the Factor Stochastic Volatility Model.

Description

fsvsample simulates from the joint posterior distribution and returns the MCMC draws. It is the main workhorse to conduct inference for factor stochastic volatility models in this package.

Usage

```
fsvsample(
 у,
  factors = 1,
  draws = 1000,
  thin = 1,
 burnin = 1000,
  restrict = "none",
  zeromean = TRUE,
  priorfacloadtype = "rowwiseng",
  priorfacload = 0.1,
  facloadtol = 1e-18,
  priorng = c(1, 1),
  priormu = c(0, 10),
  priorphiidi = c(10, 3),
  priorphifac = c(10, 3),
  priorsigmaidi = 1,
  priorsigmafac = 1,
  priorh0idi = "stationary",
  priorh0fac = "stationary",
  priorbeta = c(0, 10000),
  keeptime = "last",
  heteroskedastic = TRUE,
  priorhomoskedastic = NA,
  runningstore = 6,
  runningstorethin = 10,
  runningstoremoments = 2,
  signident = TRUE,
  signswitch = FALSE,
  interweaving = 4,
  quiet = FALSE,
  samplefac = TRUE,
  startfac,
  startpara,
  startlogvar,
  startlatent,
  startlogvar0,
```

```
startlatent0,
startfacload,
startfacloadvar,
expert
)
```

Arguments

У	Data matrix. Each of m columns is assumed to contain a single (univariate) series of length n.
factors	Number of latent factors to be estimated.
draws	Number of MCMC draws kept after burn-in.
thin	Single number greater or equal to 1, coercible to integer. Every thinth MCMC draw is kept and returned. The default value is 1, corresponding to no thinning of the draws, i.e. every draw is stored.
burnin	Number of initial MCMC draws to be discarded.
restrict	Either "upper", "none", or "auto", indicating whether the factor loadings matrix should be restricted to have zeros above the diagonal ("upper"), whether all elements should be estimated from the data ("none"), or whether the function findrestrict should be invoked for a priori finding suitable zeros. Setting restrict to "upper" or "auto" often stabilizes MCMC estimation and can be important for identifying the factor loadings matrix, however, it generally is a strong prior assumption. Setting restrict to "none" is usually the preferred option if identification of the factor loadings matrix is of less concern but covariance estimation or prediction is the goal. Alternatively, restrict can be a logical matrix of dimension $c(m, r)$ indicating which elements should be unrestricted (where restrict is FALSE) or zero (where restrict is TRUE).
zeromean	Logical. If FALSE, a constant mean is included in the model for each of the m univariate series. If TRUE, the mean is not modeled. Defaults to TRUE.
priorfacloadtyp	
	Can be "normal", "rowwiseng", "colwiseng".
	• "normal": Normal prior. The value of priorfacload is interpreted as the standard deviations of the Gaussian prior distributions for the factor loadings.
	 "rowwiseng": Row-wise Normal-Gamma prior. The value of priorfacload is interpreted as the shrinkage parameter a. "colwiseng": Column-wise Normal-Gamma prior. The value of priorfacload
	is interpreted as the shrinkage parameter a.
	For details please see Kastner (2019).
priorfacload	Either a matrix of dimensions m times factors with positive elements or a single number (which will be recycled accordingly). The meaning of priorfacload depends on the setting of priorfacloadtype and is explained there.
facloadtol	Minimum number that the absolute value of a factor loadings draw can take. Prevents numerical issues that can appear when strong shrinkage is enforced if chosen to be greater than zero.

priorng	Two-element vector with positive entries indicating the Normal-Gamma prior's hyperhyperparameters c and d.	
priormu	Vector of length 2 denoting prior mean and standard deviation for unconditional levels of the idiosyncratic log variance processes.	
priorphiidi	Vector of length 2, indicating the shape parameters for the Beta prior distribu- tions of the transformed parameters (phi+1)/2, where phi denotes the persis- tence of the idiosyncratic log variances.	
priorphifac	Vector of length 2, indicating the shape parameters for the Beta prior distribu- tions of the transformed parameters (phi+1)/2, where phi denotes the persis- tence of the factor log variances.	
priorsigmaidi	Vector of length m containing the prior volatilities of log variances. If priorsigmaidi has exactly one element, it will be recycled for all idiosyncratic log variances.	
priorsigmafac	Vector of length factors containing the prior volatilities of log variances. If priorsigmafac has exactly one element, it will be recycled for all factor log variances.	
priorh0idi	Vector of length 1 or m, containing information about the Gaussian prior for the initial idiosyncratic log variances. If an element of priorh0idi is a nonnegative number, the conditional prior of the corresponding initial log variance h0 is assumed to be Gaussian with mean 0 and standard deviation priorh0idi times \$sigma\$. If an element of priorh0idi is the string 'stationary', the prior of the corresponding initial log volatility is taken to be from the stationary distribution, i.e. h0 is assumed to be Gaussian with mean 0 and variance \$sigma^2/(1-phi^2)\$.	
priorh0fac	Vector of length 1 or factors, containing information about the Gaussian prior for the initial factor log variances. If an element of priorh@fac is a nonnega- tive number, the conditional prior of the corresponding initial log variance h0 is assumed to be Gaussian with mean 0 and standard deviation priorh@fac times \$sigma\$. If an element of priorh@fac is the string 'stationary', the prior of the corresponding initial log volatility is taken to be from the stationary distribu- tion, i.e. h0 is assumed to be Gaussian with mean 0 and variance \$sigma^2/(1- phi^2)\$.	
priorbeta	numeric vector of length 2, indicating the mean and standard deviation of the Gaussian prior for the regression parameters. The default value is $c(0, 10000)$, which constitutes a very vague prior for many common datasets. Not used if zeromean is TRUE.	
keeptime	Either a number coercible to a positive integer, or a string equal to "all" or "last". If a number different from 1 is provided, only every keeptimeth latent log- volatility is being monitored. If, e.g., keeptime = 3, draws for the latent log variances h_1, h_4, h_7, \ldots will be kept. If keeptime is set to "all", this is equivalent to setting it to 1. If keeptime is set to "last" (the default), only draws for the very last latent log variances h_n are kept.	
heteroskedastic		
	Vector of length 1, 2, or m + factors, containing logical values indicating whether time-varying (heteroskedastic = TRUE) or constant (heteroskedastic = FALSE) variance should be estimated. If heteroskedastic is of length 2 it will be recy- cled accordingly, whereby the first element is used for all idiosyncratic variances and the second element is used for all factor variances.	

priorhomoskedastic		
	Only used if at least one element of heteroskedastic is set to FALSE. In that case, priorhomoskedastic must be a matrix with positive entries and dimension $c(m, 2)$. Values in column 1 will be interpreted as the shape and values in column 2 will be interpreted as the rate parameter of the corresponding inverse gamma prior distribution of the idisyncratic variances.	
runningstore	Because most machines these days do not have enough memory to store all draws for all points in time, setting runningstore to an integer greater than 0 will cause fsvsample to store the first runningstoremoments ergodic moments of certain variables of interest. More specifically, mean, variance, skewness, etc. will be stored for certain variables if runningstore is set to a value	
	 >= 1: Latent log variances h_1, h_2,, h_(n+r). 	
	• >= 2: Latent factors f_1, \ldots, f_r .	
	 >= 3: Latent volatilities sqrt(exp(h_1,h_2,,h_(n+r))). 	
	• >= 4: Conditional covariance matrix and the square roots of its diagonal elements.	
	• >= 5: Conditional correlation matrix.	
	• >= 6: Communalities, i.e. proportions of variances explained through the common factors.	
runningstoreth		
	How often should the calculation of running moments be conducted? Set to a value > 1 if you want to avoid time consuming calculations at every MCMC iteration.	
runningstoremo		
-	Selects how many running moments (up to 4) should be calculated.	
signident	If set to FALSE, no ex-post sign-identification is performed. Defaults to TRUE.	
signswitch	Set to TRUE to turn on a random sign switch of factors and loadings. Note that the signs of each factor loadings matrix column and the corresponding factor cannot be identified from the likelihood.	
interweaving	The following values for interweaving the factor loadings are accepted:	
	• 0: No interweaving.	
	• 1: Shallow interweaving through the diagonal entries.	
	• 2: Deep interweaving through the diagonal entries.	
	• 3: Shallow interweaving through the largest absolute entries in each col- umn.	
	• 4: Deep interweaving through the largest absolute entries in each column.	
	For details please see Kastner et al. (2017). A value of 4 is the highly recommended default.	
quiet	Logical value indicating whether the progress bar and other informative out- put during sampling should be omitted. The default value is FALSE, implying verbose output.	
samplefac	If set to FALSE, the factors are not sampled (but remain at their starting values forever). This might be useful if one wants to include observed factors instead of latent ones.	

- startfac *optional* numeric matrix of dimension c(factors,n), containing the starting values of the latent factors. In case of a single factor model, a numeric vector of length n is also accepted.
- startpara
 optional numeric matrix of dimension c(3, m + factors), containing the starting values for the parameter draws. The first m columns must contain parameters values corresponding to the idiosyncratic volatilities, the subsequent factor columns must contain parameter values corresponding to the factor volatilities. The first row of startpara corresponds to mu, the level of the log variances (can be arbitrary numerical values), the second row corresponds to phi, the persistence parameters of the log variances (numeric values between -1 and 1), and the third row corresponds to sigma (positive numeric values).
- startlogvar *optional* numeric matrix of dimension c(n,m + factors), containing the starting values of the latent log variances. The first m rows correspond to the idiosyncratic log variances, the subsequent factor rows correspond to the factor log variances. Was previously called startlatent.

startlatent *Deprecated*. Please use startlogvar instead.

startlogvar0 optional numeric vector of length m + factors, containing the starting values of the initial latent log variances. The first m elements correspond to the idiosyncratic log variances, the subsequent factor elements correspond to the factor log variances. Was previously called startlatent0.

startlatent0 Deprecated. Please use startlogvar0 instead.

startfacload *optional* numeric matrix of dimension c(m, factors), containing the starting values of the factor loadings. In case of a single factor model, a numeric vector of length n is also accepted.

startfacloadvar

optional numeric matrix of dimension c(m, factors), containing the starting values of the factor loadings variances τ_{ij}^2 . Used only when the normal-gamma prior is employed (priorfacloadtype != "normal") while ignored when static loadings variances are used (priorfacloadtype == "normal").

- expert *optional* named list of expert parameters for the univariate SV models (will be transformed and passed to the stochvol package). For most applications, the default values probably work best. Interested users are referred to Kastner and Frühwirth-Schnatter (2014), the package vignette, and Kastner (2016). If expert is provided, it may contain the following named elements:
 - parameterization: Character string equal to "centered", "noncentered", "GIS_C", or "GIS_NC". Defaults to "GIS_C".
 - mhcontrol: Single numeric value controlling the proposal density of a Metropolis-Hastings (MH) update step when sampling sigma. If mhcontrol is smaller than 0, an independence proposal will be used, while values greater than zero control the stepsize of a log-random-walk proposal. Defaults to -1.
 - gammaprior: Single logical value indicating whether a Gamma prior for sigma² should be used. If set to FALSE, an Inverse Gamma prior is employed. Defaults to TRUE.
 - truncnormal: Single logical value indicating whether a truncated Gaussian distribution should be used as proposal for draws of phi. If set to FALSE, a

regular Gaussian prior is employed and the draw is immediately discarded when values outside the unit ball happen to be drawn. Defaults to FALSE.

- mhsteps: Either 1, 2, or 3. Indicates the number of blocks used for drawing from the posterior of the parameters. Defaults to 2.
- proposalvar4sigmaphi: Single positive number indicating the conditional prior variance of sigma*phi in the ridge *proposal* density for sampling (mu,phi). Defaults to 10⁸.
- proposalvar4sigmatheta: Single positive number indicating the conditional prior variance of sigma*theta in the ridge *proposal* density for sampling (mu,phi). Defaults to 10^12.

Details

For details concerning the factor SV algorithm please see Kastner et al. (2017), details about the univariate SV estimation can be found in Kastner and Frühwirth-Schnatter (2014).

Value

The value returned is a list object of class fsvdraws holding

- facload: Array containing draws from the posterior distribution of the factor loadings matrix.
- fac: Array containing factor draws from the posterior distribution.
- logvar: Array containing idiosyncratic and factor initial log variance draws.
- logvar0: Array containing idiosyncratic and factor log variance draws.
- para: Array containing parameter draws form the posterior distribution.
- y: Matrix containing the data supplied.
- latestauxiliary: List containing the latest draws of auxiliary quantities used for sampling the factor loadings matrix.
- runningstore: List whose elements contain ergodic moments of certain variables of interest. See argument runningstore for details about what is being stored here.
- config: List containing information on configuration parameters.
- priors: List containing prior hyperparameter values.
- identifier: Matrix containing the indices of the series used for ex-post sign-identification along with the corresponding minimum distances to zero. See signident for details.

To display the output, use print, plot, and in particular specialized extractors and printing functions. The print method prints a high-level overview; specialized extractors such as covmat or runningcovmat are also available. The plot method invokes a simple covariance matrix plot; specialized plotting functions are linked in the documentation of plot.fsvdraws.

References

Kastner, G., Frühwirth-Schnatter, S., and Lopes, H.F. (2017). Efficient Bayesian Inference for Multivariate Factor Stochastic Volatility Models. *Journal of Computational and Graphical Statistics*, **26**(4), 905–917, doi: 10.1080/10618600.2017.1322091.

Kastner, G. (2019). Sparse Bayesian Time-Varying Covariance Estimation in Many Dimensions *Journal of Econometrics*, **210**(1), 98–115, doi: 10.1016/j.jeconom.2018.11.007

Kastner, G. (2016). Dealing with stochastic volatility in time series using the R package stochvol. *Journal of Statistical Software*, **69**(5), 1–30, doi: 10.18637/jss.v069.i05.

Kastner, G. and Frühwirth-Schnatter, S. (2014). Ancillarity-Sufficiency Interweaving Strategy (ASIS) for Boosting MCMC Estimation of Stochastic Volatility Models. *Computational Statistics & Data Analysis*, **76**, 408–423, doi: 10.1016/j.csda.2013.01.002.

Examples

```
# Load exchange rate data (ships with stochvol):
data(exrates, package = "stochvol")
exrates$date <- NULL
# Compute the percentage log returns:
dat <- 100 * logret(exrates)
# We are going to fit a one-factor model so the ordering is irrelevant
# NOTE that these are very few draws, you probably want more...
res <- fsvsample(dat, factors = 2, draws = 2000, burnin = 1000,
runningstore = 6, zeromean = FALSE)
voltimeplot(res)
corimageplot(res, nrow(dat), plotCI = 'circle')
oldpar <- par(ask = TRUE)
plot(res)
par(oldpar)
pairs(t(res$beta[1:4, ]))
```

fsvsim

Simulate data from a factor SV model

Description

fsvsim generates simulated data from a factor SV model.

Usage

```
fsvsim(
    n = 1000,
    series = 10,
    factors = 1,
    facload = "dense",
```

fsvsim

```
idipara,
facpara,
heteroskedastic = rep(TRUE, series + factors),
df = Inf
)
```

Arguments

n	Length of the series to be generated.	
series	Number of component series m.	
factors	Number of factors r.	
facload	Can either be a matrix of dimension m times r or one of the keywords "dense" and "sparse". If "dense" is chosen, a (rather) dense lower triangular factor load- ings matrix is randomly generated. If "sparse" is chosen, a (rather) sparse lower triangular factor loadings matrix is randomly generated.	
idipara	<i>Optional</i> matrix of idiosyncratic SV parameters to be used for simulation. Must have exactly three columns containing the values of mu, phi and sigma for each of m series, respectively. If omitted, plausible values are generated.	
facpara	<i>Optional</i> matrix of idiosyncratic SV parameters to be used for simulation. Must have exactly two columns containing the values of phi and sigma for each of r factors, respectively. If omitted, plausible values are generated.	
heteroskedastic		
	Logical vector of length m+r. When TRUE, time-varying volatilities are gener- ated; when FALSE, constant volatilities (equal to mu) are generated.	
df	If not equal to Inf, the factors are misspecified (come from a t distribution instead of a Gaussian). Only used for testing.	

Value

The value returned is a list object of class fsvsim holding

- yThe simulated data, stored in a n times m matrix with colnames 'Sim1', 'Sim2', etc.
- facThe simulated factors, stored in a r times r matrix.
- facloadFactor loadings matrix.
- facvolLatent factor log-variances for times 1 to n.
- facvol0Initial factor log-variances for time 0.
- facparaThe parameters of the factor volatility processes.
- idivolLatent idiosyncratic log-variances for times 1 to n.
- idivol0Initial idiosyncratic log-variances for time 0.
- idiparaThe parameters of the idiosyncratic volatility processes.

Note

This object can be passed to many plotting functions to indicate the data generating processes when visualizing results.

ledermann

Description

In the static factor case, the Ledermann bound is the largest integer rank for which a unique decomposition of the covariance matrix is possible. (This is the largest possible number of factors which can be used for factanal.

Usage

ledermann(m)

Arguments

m

Number of component series.

Value

The Ledermann bound, a nonnegative integer.

See Also

preorder

logret

Compute the log returns of a vector-valued time series

Description

logret computes the log returns of a multivariate time series, with optional de-meaning.

Usage

```
## S3 method for class 'matrix'
logret(dat, demean = FALSE, standardize = FALSE, ...)
## S3 method for class 'data.frame'
logret(dat, demean = FALSE, standardize = FALSE, ...)
```

Arguments

dat	The raw data, a matrix or data frame with n (number of timepoints) rows and m
	(number of component series) columns.
demean	Logical value indicating whether the data should be de-meaned.
standardize	Logical value indicating whether the data should be standardized (in the sense that each component series has an empirical variance equal to one).
	Ignored.

logvartimeplot

Value

Matrix containing the log returns of the (de-meaned) data.

logvartimeplot *Plot log-variances over time*.

Description

logvartimeplot plots the idiosyncratic and factor log-variances over time.

Usage

```
logvartimeplot(x, fsvsimobj = NULL, show = "both", maxrows = 5)
```

Arguments

x	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
show	If set to "fac", only factor log-volatilities will be displayed. If set to "idi", only idiosyncratic log-volatilities will be displayed. If set to "both", factor log-volatilities will be drawn first, followed by the idiosyncratic log-volatilities.
maxrows	Indicates the maximum number of rows to be drawn per page.

Details

This function displays the posterior distribution (mean +/-2sd) of log-variances of both the factors and the idiosyncratic series. If these haven't been stored during sampling, logvartimeplot produces an error.

Value

Returns x invisibly.

See Also

Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(), facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), paratraceplot(), plot.fsvdraws(), plotalot(), voltimeplot() orderident

Description

orderident provides some (very ad-hoc) methods for identifying the ordering of the factors after running the (unrestricted) MCMC sampler by ordering according to the argument method.

Usage

```
orderident(x, method = "summed")
```

Arguments

x	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
method	Methods currently supported:
	• summean Sort by sum of mean loadings (descending).
	• summeaninv Sort by sum of mean loadings (ascending).
	• summeanabs Sort by sum of mean absolute loadings (descending).
	• summed Sort by sum of median loadings (descending).
	 summedinv Sort by sum of median loadings (ascending).
	• summedabs Sort by sum of median absolute loadings (descending).
	• maxmed Sort by maximum median loadings (descending).
	 maxmedinv Sort by maximum median loadings (ascending).
	• maxmedrel Sort by maximum median loadings, relative to the sum of all median loadings on that factor (descending).
	• maxmedabsrel Sort by maximum absolute median loadings, relative to the sum of all median loadings on that factor (descending).

Value

Returns an object of class 'fsvdraws' with adjusted ordering.

See Also

Other postprocessing: signident()

paratraceplot

Description

paratraceplot draws trace plots of all parameters (mu, phi, sigma). Can be an important tool to check MCMC convergence if inference about (certain) parameters is sought.

Usage

```
## S3 method for class 'fsvdraws'
paratraceplot(x, fsvsimobj = NULL, thinning = NULL, maxrows = 3, ...)
```

Arguments

Х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
thinning	Plot every thinningth draw.
maxrows	Indicates the maximum number of rows to be drawn per page.
	Ignored.

Value

Returns x invisibly.

See Also

```
Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(),
plot.fsvdraws(), plotalot(), voltimeplot()
```

plot.fsvdraws Default factor SV plot

Description

Displays the correlation matrix at the last sampling point in time.

Usage

```
## S3 method for class 'fsvdraws'
plot(x, quantiles = c(0.05, 0.5, 0.95), col = NULL, fsvsimobj = NULL, ...)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
quantiles	Posterior quantiles to be visualized. Must be of length 1 or 3.
col	Optional color palette.
fsvsimobj	To indicate data generating values in case of simulated data, pass an optional object of type fsvsim (usually the result of a call to fsvsim).
	Other arguments will be passed on to corrplot.

Value

Returns x invisibly.

See Also

```
Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(),
facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(),
paratraceplot(), plotalot(), voltimeplot()
```

p]	lota	lot
	Locu	τυu

Several factor SV plots useful for model diagnostics

Description

Draws a collection of plots to explore the posterior distribution of a fitted factor SV model.

Usage

```
plotalot(x, fsvsimobj = NULL, ...)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
fsvsimobj	To indicate data generating values in case of simulated data, pass an object of type fsvsim (usually the result of a call to fsvsim).
	Other arguments will be passed on to the subfunctions.

Value

Returns x invisibly.

See Also

Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(), facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(), paratraceplot(), plot.fsvdraws(), voltimeplot()

predcond

Description

predcond simulates from the posterior predictive distribution of the data, conditionally on realized values of the factors. This has the advantage that the predictive density can be written as the product of the marginals but introduces sampling uncertainty that grows with the number of factors used.

Usage

```
predcond(x, ahead = 1, each = 1, ...)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
ahead	Vector of timepoints, indicating how many steps to predict ahead.
each	Single integer (or coercible to such) indicating how often should be drawn from the posterior predictive distribution for each draw that has been stored during MCMC sampling.
	Ignored.

Value

List of class fsvpredcond containing two elements:

- meansArray containing the draws of the predictive means.
- varsArray containing the draws of the predictive variances.

See Also

Other predictors: predcor(), predcov(), predh(), predloglikWB(), predloglik(), predprecWB()

Examples

predcor

```
# Visualize the predictive distribution
pairs(t(preddraws), col = rgb(0,0,0,.1), pch = 16)
```

predcor

Predicts correlation matrix

Description

predcor simulates from the posterior predictive distribution of the model-implied correlation matrix.

Usage

predcor(x, ahead = 1, each = 1)

Arguments

x	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
ahead	Vector of timepoints, indicating how many steps to predict ahead.
each	Single integer (or coercible to such) indicating how often should be drawn from the posterior predictive distribution for each draw that has been stored during MCMC sampling.

Value

4-dimensional array containing draws from the predictive correlation distribution.

Note

Currently crudely implemented as a triple loop in pure R, may be slow.

See Also

Other predictors: predcond(), predcov(), predh(), predloglikWB(), predloglik(), predprecWB()

Examples

```
set.seed(1)
sim <- fsvsim(series = 3, factors = 1) # simulate
res <- fsvsample(sim$y, factors = 1) # estimate
# Predict 1, 10, and 100 days ahead:
predobj <- predcor(res, ahead = c(1, 10, 100))
# Trace plot of draws from posterior predictive distribution
# of the correlation of Sim1 and Sim2:
```

36

predcov

```
# (one, ten, and 100 days ahead):
plot.ts(predobj[1,2,,])
# Smoothed kernel density estimates of predicted covariance
# of Sim1 and Sim2:
plot(density(predobj[1,2,,"1"], adjust = 2))
lines(density(predobj[1,2,,"10"], adjust = 2), col = 2)
lines(density(predobj[1,2,,"100"], adjust = 2), col = 3)
```

predcov

Predicts covariance matrix

Description

predcov simulates from the posterior predictive distribution of the model-implied covariance matrix.

Usage

```
predcov(x, ahead = 1, each = 1)
```

Arguments

Х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
ahead	Vector of timepoints, indicating how many steps to predict ahead.
each	Single integer (or coercible to such) indicating how often should be drawn from the posterior predictive distribution for each draw that has been stored during MCMC sampling.

Value

4-dimensional array containing draws from the predictive covariance distribution.

Note

Currently crudely implemented as a triple loop in pure R, may be slow.

See Also

Other predictors: predcond(), predcor(), predh(), predloglikWB(), predloglik(), predprecWB()

Examples

```
set.seed(1)
sim <- fsvsim(series = 3, factors = 1) # simulate
res <- fsvsample(sim$y, factors = 1) # estimate
# Predict 1, 10, and 100 days ahead:
predobj <- predcov(res, ahead = c(1, 10, 100))
# Trace plot of draws from posterior predictive distribution
# of the covariance of Sim1 and Sim2:
 # (one, ten, and 100 days ahead):
plot.ts(predobj[1,2,,])
# Smoothed kernel density estimates of predicted covariance
# of Sim1 and Sim2:
plot(density(predobj[1,2,,"1"], adjust = 2))
lines(density(predobj[1,2,,"10"], adjust = 2), col = 2)
lines(density(predobj[1,2,,"100"], adjust = 2), col = 3)
```

predh

Predicts factor and idiosyncratic log-volatilities h

Description

predh simulates from the posterior predictive distribution of the latent log-variances h, both for factors as well as for idiosyncratic series.

Usage

predh(x, ahead = 1, each = 1)

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
ahead	Vector of timepoints, indicating how many steps to predict ahead.
each	Single integer (or coercible to such) indicating how often should be drawn from the posterior predictive distribution for each draw that has been stored during MCMC sampling.

Value

List of class fsvpredh containing two elements:

- idihArray containing the draws of the latent idiosyncratic log-volatilities.
- factorhArray containing the draws of the latent factor log-volatilities.

38

predloglik

See Also

Other predictors: predcond(), predcor(), predcov(), predloglikWB(), predloglik(), predprecWB()

Examples

```
set.seed(1)
sim <- fsvsim(series = 3, factors = 1) # simulate
res <- fsvsample(sim$y, factors = 1) # estimate
# Predict 1, 10, and 100 days ahead:
predobj <- predh(res, ahead = c(1, 10, 100))
# Trace plot of draws from posterior predictive factor log-variance
# (one, ten, and 100 days ahead):
plot.ts(predobj$factorh[1,,])
# Smoothed kernel density estimates of predicted volas:
plot(density(exp(predobj$factorh[1,,"1"]/2), adjust = 2))
lines(density(exp(predobj$factorh[1,,"10"]/2), adjust = 2), col = 2)
lines(density(exp(predobj$factorh[1,,"10"]/2), adjust = 2), col = 3)
```

predloglik	Evaluates the predictive log likelihood using the predicted covariance
	matrix

Description

predloglik approximates the predictive log likelihood by simulating from the predictive distribution of the covariance matrix and evaluating the corresponding multivariate normal distribution.

Usage

```
predloglik(
    x,
    y,
    ahead = 1,
    each = 1,
    alldraws = FALSE,
    indicator = rep(TRUE, ncol(y))
)
```

Arguments

Х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
У	Matrix of dimension length(ahead) times m where the predictive density should
	be evaluated.

ahead	Vector of timepoints, indicating how many steps to predict ahead.
each	Single integer (or coercible to such) indicating how often should be drawn from the posterior predictive distribution for each draw that has been stored during MCMC sampling.
alldraws	Should all the draws be returned or just the final results? (Can be useful to assess convergence.)
indicator	Logical vector of length m indicating which component series should be evalu- ated. The default is to evaluate all of them.

Value

Vector of length length(ahead) with log predictive likelihoods.

See Also

Uses predcov. If m is large but only few factors are used, consider also using predloglikWB.

Other predictors: predcond(), predcor(), predcov(), predh(), predloglikWB(), predprecWB()

Examples

```
set.seed(1)
# Simulate a time series of length 1100:
sim <- fsvsim(n = 1100, series = 3, factors = 1)
y <- sim$y
# Estimate using only 1000 days:
res <- fsvsample(y[seq_len(1000),], factors = 1)
# Evaluate the 1, 10, and 100 days ahead predictive log
# likelihood:
ahead <- c(1, 10, 100)
scores <- predloglik(res, y[1000+ahead,], ahead = ahead, each = 10)
print(scores)</pre>
```

predloglikWB Evaluates the

Evaluates the predictive log likelihood using the Woodbury identity

Description

predloglikWB approximates the predictive log likelihood exploiting the factor structure and using the Woodbury identity and the corresponding matrix determinant lemma. This is recommended only if many series and few factors are present.

predloglikWB

Usage

predloglikWB(x, y, ahead = 1, each = 1, alldraws = FALSE)

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
У	Matrix of dimension length(ahead) times m where the predictive density should be evaluated.
ahead	Vector of timepoints, indicating how many steps to predict ahead.
each	Single integer (or coercible to such) indicating how often should be drawn from the posterior predictive distribution for each draw that has been stored during MCMC sampling.
alldraws	Should all the draws be returned or just the final results? (Can be useful to assess convergence.)

Value

Vector of length length(ahead) with log predictive likelihoods.

Note

Currently crudely implemented as a triple loop in pure R, may be slow.

See Also

Uses predprecWB. If m is small or many factors are used, consider also using predcov.

Other predictors: predcond(), predcor(), predcov(), predh(), predloglik(), predprecWB()

Examples

```
set.seed(1)
# Simulate a time series of length 1100:
sim <- fsvsim(n = 1100, series = 3, factors = 1)
y <- sim$y
# Estimate using only 1000 days:
res <- fsvsample(y[seq_len(1000),], factors = 1)
# Evaluate the 1, 10, and 100 days ahead predictive log
# likelihood:
ahead <- c(1, 10, 100)
scores <- predloglikWB(res, y[1000+ahead,], ahead = ahead, each = 10)
print(scores)</pre>
```

predprecWB

Description

predprecWB simulates from the posterior predictive distribution of the model-implied precision matrix and its determinant using the Woodbury matrix identity and the matrix determinant lemma

Usage

predprecWB(x, ahead = 1, each = 1)

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
ahead	Vector of timepoints, indicating how many steps to predict ahead.
each	Single integer (or coercible to such) indicating how often should be drawn from the posterior predictive distribution for each draw that has been stored during MCMC sampling.

Value

List containing two elements:

- precisionArray containing the draws of the predicted precision matrix.
- precisionlogdetMatrix containing the draws of the determinant of the predicted precision matrix.

Note

Currently crudely implemented as a triple loop in pure R, may be slow.

See Also

Usually used for evaluating the predictive likelihood when many series but few factors are used, see predloglik and predloglikWB.

Other predictors: predcond(), predcor(), predcov(), predh(), predloglikWB(), predloglik()

preorder

Description

In factor SV models, the ordering of variables is often chosen through a preliminary static factor analysis. These methods are implemented in preorder. After a maximum likelihood factor model fit to the data, factor loadings are ordered as follows: The variable with the highest loading on factor 1 is placed first, the variable with the highest loading on factor 2 second (unless this variable is already placed first, in which case the variable with the second highest loading is taken).

Usage

```
preorder(
   dat,
   factors = ledermann(ncol(dat)),
   type = "fixed",
   transload = identity
)
```

Arguments

dat	Matrix containing the data, with n rows (points in time) and m columns (component series).
factors	Number of factors to be used, defaults to the Ledermann bound.
type	Can be "fixed" or "dynamic". The option "fixed" means that that a factors- factor model is fit once and the entire ordering is determined according to this fit (the default). The option "dynamic" means that the model is re-fit factors times with the number of factors going from 1 to factors and in each round the correspondingly largest loading is chosen.
transload	Function for transforming the estimated factor loadings before ordering. De- faults to the identity function.

Value

A vector of length m with the ordering found.

See Also

ledermann

print.fsvdraws

Description

Pretty printing of an fsvsdraws object

Usage

```
## S3 method for class 'fsvdraws'
print(x, ...)
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call of fsvsample.
	Ignored.

Value

Returns x invisibly.

runningcormat	Extract summary statistics for the posterior correlation matrix which
	have been stored during sampling

Description

runningcormat extracts summary statistics from the model-implied correlation matrix from an fsvdraws object for one point in time.

Usage

```
runningcormat(x, i, statistic = "mean", type = "cor")
```

Arguments

х	Object of class 'fsvdraws', usually resulting from a call of fsvsample.
i	A single point in time.
statistic	Indicates which statistic should be extracted. Defaults to 'mean'.
type	Indicates whether covariance (cov) or correlation (cor) should be extracted.

Value

Matrix containing the requested correlation matrix summary statistic.

runningcovmat

See Also

Other extractors: cormat.fsvdraws(), covmat.fsvdraws(), runningcovmat()

Examples

```
set.seed(1)
sim <- fsvsim(n = 500, series = 3, factors = 1) # simulate</pre>
res <- fsvsample(sim$y, factors = 1, runningstore = 6) # estimate</pre>
cor100mean <- runningcormat(res, 100) # extract mean at t = 100</pre>
cor100sd <- runningcormat(res, 100, statistic = "sd") # extract sd</pre>
lower <- cor100mean - 2*cor100sd</pre>
upper <- cor100mean + 2*cor100sd
true <- cormat(sim, 100)[,,1] # true value</pre>
# Visualize mean +/- 2sd and data generating values
par(mfrow = c(3,3), mar = c(2, 2, 2, 2))
for (i in 1:3) {
 for (j in 1:3) {
  plot(cor100mean[i,j], ylim = range(lower, upper), pch = 3,
  main = paste(i, j, sep = ' vs. '), xlab = '', ylab = '')
  lines(c(1,1), c(lower[i,j], upper[i,j]))
  points(true[i,j], col = 3, cex = 2)
 }
}
```

runningcovmat	Extract summary statistics for the posterior covariance matrix which
	have been stored during sampling

Description

runningcovmat extracts summary statistics from the model-implied covariance matrix from an fsvdraws object for one point in time.

Usage

```
runningcovmat(x, i, statistic = "mean", type = "cov")
```

Arguments

Х	Object of class 'fsvdraws', usually resulting from a call of fsvsample.
i	A single point in time.
statistic	Indicates which statistic should be extracted. Defaults to 'mean'.
type	Indicates whether covariance (cov) or correlation (cor) should be extracted.

Value

Matrix containing the requested covariance matrix summary statistic.

See Also

Other extractors: cormat.fsvdraws(), covmat.fsvdraws(), runningcormat()

Examples

```
set.seed(1)
sim <- fsvsim(n = 500, series = 3, factors = 1) # simulate</pre>
res <- fsvsample(sim$y, factors = 1) # estimate</pre>
cov100mean <- runningcovmat(res, 100) # extract mean at t = 100</pre>
cov100sd <- runningcovmat(res, 100, statistic = "sd") # extract sd</pre>
lower <- cov100mean - 2*cov100sd</pre>
upper <- cov100mean + 2*cov100sd
true <- covmat(sim, 100) # true value</pre>
# Visualize mean +/- 2sd and data generating values
par(mfrow = c(3,3), mar = c(2, 2, 2, 2))
for (i in 1:3) {
 for (j in 1:3) {
  plot(cov100mean[i,j], ylim = range(lower, upper), pch = 3,
  main = paste(i, j, sep = ' vs. '), xlab = '', ylab = '')
  lines(c(1,1), c(lower[i,j], upper[i,j]))
  points(true[i,j,1], col = 3, cex = 2)
 }
}
```

signident

A posteriori sign identification

Description

signident provides methods for identifying the signs of the factor loadings after running the MCMC sampler

Usage

```
signident(x, method = "maximin", implementation = 3)
```

46

voltimeplot

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
method	Can be "diagonal" or "maximin". If "diagonal" is chosen, the diagonal ele- ments of the factor loadings matrix are assumed to have positive signs and the others are arranged accordingly. If "maximin" is chosen, for each fac- tor, signident looks for the series where the minimum absolute loadings are biggest and chooses this series to have positive loadings.
implementation	Either 1, 2, or 3 (the default). Determines how the reordering is implemented. Should not be necessary to depart from the default.

Value

Returns an object of class 'fsvdraws' with adjusted factors and factor loadings. Moreover, a list element called 'identifier' is added, providing the numbers of the series used for identification and the corresponding minimum distances to zero.

See Also

Other postprocessing: orderident()

Examples

voltimeplot

Plot series-specific volatilities over time.

Description

voltimeplot plots the marginal volatilities over time, i.e. the series-specific conditional standard deviations. If these haven't been stored during sampling (because runningstore has been set too low), voltimeplot throws a warning.

Usage

voltimeplot(x, these = seq_len(nrow(x\$y)), legend = "topright", ...)

Arguments

х	Object of class 'fsvdraws', usually resulting from a call to fsvsample.
these	Index vector containing the time points to plot. Defaults to seq_len(nrow(x\$y)), i.e., all timepoints.
legend	Where to position the legend. If set to NULL, labels will be put directly next to the series. Defaults to "topright".
	Additional parameters will be passed on to ts.plot.

Value

Returns x invisibly.

See Also

Other plotting: comtimeplot(), corimageplot(), corplot(), cortimeplot(), evdiag(), facloadcredplot(), facloaddensplot(), facloadpairplot(), facloadpointplot(), facloadtraceplot(), logvartimeplot(), paratraceplot(), plot.fsvdraws(), plotalot()

Index

* extractors cormat.fsvdraws,8 covmat.fsvdraws, 13 runningcormat, 44 runningcovmat, 45 * generics cormat, 8 covmat, 13 * models factorstochvol-package, 3 * package factorstochvol-package, 3 * plotting comtimeplot, 5 corimageplot, 6 corplot, 10 cortimeplot, 11 evdiag, 15 facloadcredplot, 17 facloaddensplot, 17 facloadpairplot, 18 facloadpointplot, 19 facloadtraceplot, 20 logvartimeplot, 31 paratraceplot, 33 plot.fsvdraws, 33 plotalot, 34 voltimeplot, 47 * postprocessing orderident, 32 signident, 46 * predictors predcond, 35 predcor, 36 predcov, 37 predh, 38 predloglik, 39 predloglikWB, 40 predprecWB, 42

* printing print.fsvdraws, 44 * simulation corelement, 6 cormat.fsvsim,9 covelement. 12 covmat.fsvsim, 15 * ts factorstochvol-package, 3 * wrappers fsvsample, 22 comtimeplot, 5, 7, 11, 12, 16-20, 31, 33, 34, 48 corelement, 6, 10, 13, 15 corimageplot, 5, 6, 11, 12, 16-20, 31, 33, 34, 48 cormat, 8, 13 cormat.fsvdraws, 8, 8, 14, 45, 46 cormat.fsvsim, 6, 8, 9, 13, 15 corplot, 5, 7, 10, 12, 16-20, 31, 33, 34, 48 corrMatOrder, 7 corrplot, 7, 34 cortimeplot, 5, 7, 11, 11, 16-20, 31, 33, 34, 48 covelement, 6, 10, 12, 15 covmat, 8, 13, 27 covmat.fsvdraws, 9, 13, 13, 45, 46 covmat.fsvsim, 6, 10, 13, 15 covtimeplot (cortimeplot), 11 evdiag, 5, 7, 11, 12, 15, 17-20, 31, 33, 34, 48 expweightcov, 16 facloadcredplot, 5, 7, 11, 12, 16, 17, 18-20, 31, 33, 34, 48 facloaddensplot, 5, 7, 11, 12, 16, 17, 17, 18–20, 31, 33, 34, 48 facloadpairplot, 5, 7, 11, 12, 16-18, 18, 19,

20, 31, 33, 34, 48

INDEX

facloadpointplot, 5, 7, 11, 12, 16-18, 19, 20, 31, 33, 34, 48 facloadtraceplot, 5, 7, 11, 12, 16–19, 20, 31, 33, 34, 48 factanal, 30 factorstochvol-package, 3 findrestrict, 21, 23 fsvsample, 5, 7, 8, 11, 12, 14, 16-20, 22, 31-39, 41, 42, 44, 45, 47, 48 fsvsim, 5-7, 10-12, 15, 17, 19, 20, 28, 31, 33, 34 image, 7 ledermann, 30 legend, 48 logret, 30 logvartimeplot, 5, 7, 11, 12, 16-20, 31, 33, 34,48 orderident, 32, 47 paratraceplot, 5, 7, 11, 12, 16-20, 31, 33, 34,48 plot.fsvdraws, 5, 7, 11, 12, 16-20, 27, 31, 33, 33, 34, 48 plotalot, 5, 7, 11, 12, 16-20, 31, 33, 34, 34, 48 predcond, 35, 36, 37, 39-42 predcor, 35, 36, 37, 39-42 predcov, 35, 36, 37, 39-42 predh, 35-37, 38, 40-42 predloglik, 35-37, 39, 39, 41, 42 predloglikWB, 35-37, 39, 40, 40, 42 predprecWB, 35-37, 39-41, 42 preorder, 43 print.fsvdraws,44

rgb, *19* runningcormat, *9*, *14*, 44, *46* runningcovmat, *9*, *14*, *27*, *45*, 45

signident, *27*, *32*, 46 stochvol, *4*

ts.plot, *11*, *48*

voltimeplot, 5, 7, 11, 12, 16–20, 31, 33, 34, 47

50