Package 'georob'

June 4, 2021

Type Package
Title Robust Geostatistical Analysis of Spatial Data
Version 0.3-14
Date 2021-06-04
Depends R(>= 2.14.0), graphics, parallel, snowfall, sp(>= 0.9-60), stats, utils
Imports abind, constrainedKriging(>= 0.2-1), fields, lmtest, methods, nlme, nleqslv, quantreg, RandomFields(>= 3.3.6), robustbase(>= 0.90-2)
Suggests gstat, multcomp, lattice
Description Provides functions for efficiently fitting linear models with spatially correlated errors by robust and Gaussian (Restricted) Maximum Likelihood and for computing robust and customary point and block external-drift Kriging predictions, along with utility functions for variogram modelling in ad hoc geostatistical analyses, model building, model evaluation by cross-validation, (conditional) simulation of Gaussian processes, unbiased back-transformation of Kriging predictions of log-transformed data.
License GPL (>= 2) LGPL (>= 2)
NeedsCompilation no
Author Andreas Papritz [cre, aut], Cornelia Schwierz [ctb]
Maintainer Andreas Papritz <andreas.papritz@env.ethz.ch></andreas.papritz@env.ethz.ch>
Repository CRAN
Date/Publication 2021-06-04 09:30:02 UTC
R topics documented:
compress

2 compress

	elevation	
	georob	
	georobModelBuilding	
	georobObject	34
	georobPackage	37
	georobS3methods	41
	georobSimulation	45
	lgnpp	49
	param.names	54
	plot.georob	55
	pmm	58
	predict.georob	60
	profilelogLik	64
	sample.variogram	66
	validate.predictions	71
	wolfcamp	75
Index		77

Description

compress

The utility function compress stores symmetric or triangular matrices compactly by retaining only the diagonal and either the lower or upper off-diagonal elements. The function expand restores such compressed matrices again to a square form.

Compact Storage of Symmetric and Triangular Matrices

Usage

```
compress(m)
expand(object)
```

Arguments

m

either a single symmetric, lower or upper triangular matrix or a list of such matrices. The type of m (or of its component matrices) must be defined by the attribute struc with possible values "sym" (symmetric), "lt" (lower triangular) or "ut" (upper triangular).

object

a single compressed matrix or a list of such matrices generated by compress, see *Value*. The type of object (or of its components) must be defined by the attribute struc with possible values "sym" (symmetric), "lt" (lower triangular) or "ut" (upper triangular).

Value

If m is a single square matrix then compress generates a compressed matrix, which is a list with two components:

diag a vector with the diagonal elements of m.

tri a vector with non-redundant off-diagonal elements.

If m is a list of square matrices then the result is also a list of compressed matrices.

expand creates a square matrix if object is a list with components diag and tri and a list of square matrices if object is a list of such lists. If m or objects are lists that contain other components than squared or compressed matrices then these additional components are returned unchanged.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

georob for (robust) fitting of spatial linear models.

Examples

```
## Not run:
data(meuse)

r.logzn.rob <- georob(log(zinc) ~ sqrt(dist) + ffreq, data = meuse, locations = ~ x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1)

cov2cor(expand(r.logzn.rob[["cov"]][["cov.betahat"]]))

## End(Not run)</pre>
```

control.georob

Control Parameters for georob

Description

This page documents parameters used to control georob. It describes the arguments of the functions control.georob, param.transf, fwd.transf, dfwd.transf, bwd.transf, control.rq, control.nleqslv, control.nlminb and control.optim, which all serve to control the behaviour of georob.

Usage

```
control.georob(ml.method = c("REML", "ML"), reparam = TRUE,
   maximizer = c("nlminb", "optim"), initial.param = TRUE,
    initial.fixef = c("lmrob", "rq", "lm"), bhat = NULL,
   min.rweight = 0.25,
    param.tf = param.transf(), fwd.tf = fwd.transf(),
    deriv.fwd.tf = dfwd.transf(), bwd.tf = bwd.transf(),
   psi.func = c("logistic", "t.dist", "huber"),
    irwls.maxiter = 50,
    irwls.ftol = 1.e-5, force.gradient = FALSE,
   min.condnum = 1.e-12, zero.dist = sqrt(.Machine[["double.eps"]]),
   error.family.estimation = c("gaussian", "long.tailed"),
    error.family.cov.effects = c("gaussian", "long.tailed"),
   error.family.cov.residuals = c("gaussian", "long.tailed"),
   cov.bhat = TRUE, full.cov.bhat = FALSE, cov.betahat = TRUE,
   cov.delta.bhat = TRUE, full.cov.delta.bhat = TRUE,
   cov.delta.bhat.betahat = TRUE,
   cov.ehat = TRUE, full.cov.ehat = FALSE,
   cov.ehat.p.bhat = FALSE, full.cov.ehat.p.bhat = FALSE,
   hessian = TRUE,
   rq = control.rq(), lmrob = lmrob.control(),
    nleqslv = control.nleqslv(),
    optim = control.optim(), nlminb = control.nlminb(),
    pcmp = control.pcmp(), ...)
param.transf(variance = "log", snugget = "log", nugget = "log", scale = "log",
   alpha = c(
   RMaskey = "log", RMdewijsian = "logit2", RMfbm = "logit2", RMgencauchy = "logit2",
   RMgenfbm = "logit2", RMlgd = "identity", RMqexp = "logit1", RMstable = "logit2"
   beta = c(RMdagum = "logit1", RMgencauchy = "log", RMlgd = "log"),
   delta = "logit1", gamma = c(RMcauchy = "log", RMdagum = "logit1"),
   kappa = "logit3", lambda = "log", mu = "log", nu = "log",
   f1 = "log", f2 = "log", omega = "identity", phi = "identity", zeta = "identity")
fwd.transf(...)
dfwd.transf(...)
bwd.transf(...)
control.rq(tau = 0.5, rq.method = c("br", "fnb", "pfn"),
    rq.alpha = 0.1, ci = FALSE, iid = TRUE,
    interp = TRUE, tcrit = TRUE, rq.beta = 0.99995, eps = 1e-06,
   Mm.factor = 0.8, max.bad.fixup = 3, ...)
control.nleqslv(method = c("Broyden", "Newton"),
   global = c("dbldog", "pwldog", "qline", "gline", "none"),
```

Arguments

ml.method character keyword defining whether non-robust maximum likelihood (ML) or re-

stricted maximum likelihood (REML default) estimates will be computed (ignored

if tuning.psi <= tuning.psi.nr).</pre>

reparam logical. If TRUE (default) the re-parametrized variance parameters σ_B^2 , η and ξ

are estimated by Gaussian (RE)ML, otherwise the original parameters τ^2 , σ_n^2 and σ^2 (cf. subsection *Estimating variance parameters by Gaussian (RE)ML*,

section *Details* of georob).

maximizer character keyword defining whether the Gaussian (restricted) log-likelihood is

maximized by nlminb (default) or optim.

initial.param logical, controlling whether initial values of variogram parameters are computed

for solving the estimating equations of the variogram and anisotropy parameters. If initial.param = TRUE (default) robust initial values of parameters are computed by discarding outlying observations based on the "robustness weights" of the initial fit of the regression model by lmrob and fitting the spatial linear model by Gaussian REML to the pruned data set. For initial.param = FALSE no initial parameter values are computed and the estimating equations are solved with

the initial values passed by param and aniso to georob (see *Details* of georob).

initial.fixef character keyword defining whether the function lmrob or rq is used to compute

robust initial estimates of the regression parameters β (default "1mrob"). If the fixed effects model matrix has not full columns rank, then 1m is used to compute

initial values of the regression coefficients.

bhat initial values for the spatial random effects \hat{B} , with $\hat{B}=0$ if bhat is equal to

NULL (default).

min.rweight positive numeric. "Robustness weight" of the initial lmrob fit that observations

must exceed to be used for computing robust initial estimates of variogram pa-

rameters by setting initial.param = TRUE (see georob; default 0.25).

param.tf a function such as param.transf, which returns a named list of character strings

that define the transformations to be applied to the variogram parameters for

model fitting, see Details.

fwd.tf a function such as fwd.transf, which returns a named list of invertible func-

tions to be used to transform variogram parameters, see *Details*.

deriv.fwd.tf a function such as dfwd.transf, which returns a named list of functions corre-

sponding to the first derivatives of fwd.tf, see Details.

a function such as bwd. transf, which returns the named list of inverse functions bwd.tf corresponding to fwd. tf, see Details. psi.func character keyword defining what ψ_c -function should be used for robust model fitting. Possible values are "logistic" (a scaled and shifted logistic CDF, default), "t.dist" (re-descending ψ_c -function associated with Student t-distribution with c degrees of freedom) and "huber" (Huber's ψ_c -function). positive integer equal to the maximum number of IRWLS iterations to solve the irwls.maxiter estimating equations of B and β (default 50). irwls.ftol positive numeric convergence criterion for IRWLS. Convergence is assumed if the objective function changes in one IRWLS iteration does not exceed ftol. force.gradient logical controlling whether the estimating equations or the gradient of the Gaussian restricted log-likelihood are evaluated even if all variogram parameters are fixed (default FALSE). positive numeric. Minimum acceptable ratio of smallest to largest singular value min.condnum of the model matrix X (default 1.e-12). zero.dist positive numeric equal to the maximum distance, separating two sampling locations that are still considered as being coincident. error.family.estimation character keyword, defining the probability distribution for ε (default: "gaussian") that is used to approximate the covariance of \widehat{B} when solving the estimating equations, see Details. error.family.cov.effects character keyword, defining the probability distribution for ε (default: "gaussian") that is used to approximate the covariances of $\widehat{\beta}$, \widehat{B} and $B - \widehat{B}$, see *Details*. error.family.cov.residuals character keyword, defining the probability distribution for ε (default: "long.tailed") that is used to approximate the covariances of $\hat{\varepsilon} = Y - X\hat{\beta}$ – \widehat{B} and $\widehat{\varepsilon} + \widehat{B} = Y - X\widehat{\beta}$, see *Details*. logical controlling whether the covariances of \widehat{B} are returned by georob (default cov.bhat FALSE). logical controlling whether the full covariance matrix (TRUE) or only the varifull.cov.bhat ance vector of \vec{B} is returned (default FALSE). logical controlling whether the covariance matrix of $\hat{\beta}$ is returned (default TRUE). cov.betahat cov.delta.bhat logical controlling whether the covariances of $B-\widehat{B}$ are returned (default TRUE). full.cov.delta.bhat logical controlling whether the full covariance matrix (TRUE) or only the variance vector of $B - \hat{B}$ is returned (default TRUE). cov.delta.bhat.betahat logical controlling whether the covariance matrix of $B - \hat{B}$ and $\hat{\beta}$ is returned (default TRUE). logical controlling whether the covariances of $\hat{\epsilon} = Y - X\hat{\beta} - \hat{B}$ are returned cov.ehat (default TRUE).

logical controlling whether the full covariance matrix (TRUE) or only the varifull.cov.ehat ance vector of $\hat{\boldsymbol{\varepsilon}} = \boldsymbol{Y} - \boldsymbol{X} \hat{\boldsymbol{\beta}} - \hat{\boldsymbol{B}}$ is returned (default FALSE). cov.ehat.p.bhat logical controlling whether the covariances of $\hat{\epsilon} + \hat{B} = Y - X\hat{\beta}$ are returned (default FALSE). full.cov.ehat.p.bhat logical controlling whether the full covariance matrix (TRUE) or only the variance vector of $\hat{\boldsymbol{\varepsilon}} + \hat{\boldsymbol{B}} = \boldsymbol{Y} - \boldsymbol{X}\hat{\boldsymbol{\beta}}$ is returned (default FALSE). hessian logical scalar controlling whether for Gaussian (RE)ML the Hessian should be computed at the MLEs. rq a list of arguments passed to rq or a function such as control.rq that generates such a list (see rq for allowed arguments). 1mrob a list of arguments passed to the control argument of 1mrob or a function such as lmrob.control that generates such a list (see lmrob.control for allowed arguments). nlegslv a list of arguments passed to nleqsly or a function such as control.nleqsly that generates such a list (see nleqslv for allowed arguments). nlminb a list of arguments passed to nlminb or a function such as control.nlminb that generates such a list (see nlminb for allowed arguments). a list of arguments passed to optim or a function such as control.optim that optim generates such a list (see optim for allowed arguments). a list of arguments, passed e.g. to pmm or a function such as control.pcmp that pcmp generates such a list (see control.pcmp for allowed arguments). for fwd. transf, dfwd. transf and bwd. transf a named vectors of functions, extending the definition of transformations for variogram parameters (see Details). variance, snugget, nugget, scale, alpha, beta, delta, gamma, kappa, lambda, mu, nu character strings with names of transformation functions of the variogram parameters. f1, f2, omega, phi, zeta character strings with names of transformation functions of the variogram parameters. tau, rq.method, rq.alpha, ci, iid, interp, tcrit arguments passed as ... to rq. Note that only "br", "fnb" and "pfn" methods of rq() are currently supported. rq.beta, eps, Mm.factor, max.bad.fixup arguments passed as . . . to rq. method, global, xscalm, control, lower, upper, reltol, rel.tol arguments passed to related arguments of nlegsly, nlminb and optim, respectively.

Details

Parameter transformations:

The arguments param.tf, fwd.tf, deriv.fwd.tf, bwd.tf define the transformations of the variogram parameters for RE(ML) estimation. Implemented are currently "log", "logit1", "logit2", "logit3" (various variants of logit-transformation, see code of function fwd.transf) and "identity" (= no) transformations. These are the possible values that the many arguments of the function param.transf accept (as quoted character strings) and these are the names of the list components returned by fwd.transf, dfwd.transf and bwd.transf. Additional transformations can be implemented by:

- 1. Extending the function definitions by arguments like
 fwd.tf = fwd.transf(my.fun = function(x) your transformation),
 deriv.fwd.tf = dfwd.transf(my.fun = function(x) your derivative),
 bwd.tf = bwd.transf(my.fun = function(x) your back-transformation),
- 2. Assigning to a given argument of param. transf the name of the new function, e.g. variance = "my.fun".

Note the values given for the arguments of param. transf must match the names of the functions returned by fwd.transf, dfwd.transf and bwd.transf.

Approximation of covariances of fixed and random effects and residuals:

The robustified estimating equations of robust REML depend on the covariances of \widehat{B} . These covariances (and the covariances of $B-\widehat{B},\widehat{\beta},\widehat{\varepsilon},\widehat{\varepsilon}+\widehat{B}$) are approximated by expressions that in turn depend on the variances of ε , $\psi(\varepsilon/\tau)$ and the expectation of $\psi'(\varepsilon/\tau)(=\partial/\partial\varepsilon\,\psi(\varepsilon/\tau))$. The arguments error family estimation, error family coverfects and error family coveresiduals control what parametric distribution for ε is used to compute the variance of ε , $\psi(\varepsilon/\tau)$ and the expectation of $\psi'(\varepsilon/\tau)$ when

- solving the estimating equations (error.family.estimation),
- computing the covariances of $\widehat{m{eta}}, \widehat{m{B}}$ and $m{B} \widehat{m{B}}$ (error.family.cov.effects) and
- computing the covariances of $\hat{\varepsilon} = Y X\hat{\beta} \hat{B}$ and $\hat{\varepsilon} + \hat{B} = Y X\hat{\beta}$ (error.family.cov.residuals).

Possible options are: "gaussian" or "long.tailed". In the latter case the PDF of ε is assumed to be proportional to $1/\tau \exp(-\rho(\varepsilon/\tau))$, where $\psi(x) = \rho'(x)$.

Value

control.georob, control.rq, control.nleqslv, control.optim and control.nlminb all create lists with control parameters passed to georob, rq, nleqslv, optim, nlminb, respectively. Note that the list returned by code.georob contains some components (irwls.initial, tuning.psi.nr, cov.bhat.betahat, aux.cov.pred.target) that cannot be changed by the user.

param.transf generates a list with character strings that define what transformations are used for estimating the variogram parameters, and fwd.transf, bwd.transf and dfwd.transf return lists of functions with forward and backward transformations and the first derivatives of the forward transformations.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

cv 9

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; georobObject for a description of the class georob; profilelogLik for computing profiles of Gaussian likelihoods; plot.georob for display of RE(ML) variogram estimates; georobModelBuilding for stepwise building models of class georob; cv.georob for assessing the goodness of a fit by georob; georobMethods for further methods for the class georob; predict.georob for computing robust Kriging predictions; lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data; georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

Examples

```
## Not run:
data(meuse)

r.logzn.rob <- georob(log(zinc) ~ sqrt(dist), data = meuse, locations = ~ x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1, control = control.georob(cov.bhat = TRUE,
    cov.ehat.p.bhat = TRUE, initial.fixef = "rq"), verbose = 2)

qqnorm(rstandard(r.logzn.rob, level = 0)); abline(0, 1)
qqnorm(ranef(r.logzn.rob, standard = TRUE)); abline(0, 1)

## End(Not run)</pre>
```

cv

Generic Cross-validation

Description

Generic function for cross-validating models.

Usage

```
cv(object, ...)
```

Arguments

```
object any model object.... additional arguments as required by the methods.
```

Value

will depend on the method function used; see the respective documentation.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

```
georob for (robust) fitting of spatial linear models;
cv.georob for assessing the goodness of a model fitted by georob.
```

cv.georob

Cross-Validating a Spatial Linear Model Fitted by georob

Description

This function assesses the goodness-of-fit of a spatial linear model by K-fold cross-validation. In more detail, the model is re-fitted K times by robust (or Gaussian) (RE)ML, excluding each time 1/Kth of the data. The re-fitted models are used to compute robust (or customary) external Kriging predictions for the omitted observations. If the response variable is log-transformed then the Kriging predictions can be optionally transformed back to the original scale of the measurements. S3methods for evaluating and plotting diagnostic summaries of the cross-validation errors are described for the function validate.predictions.

Usage

```
## S3 method for class 'georob'
cv(object, formula = NULL, subset = NULL,
    method = c("block", "random"), nset = 10L, seed = NULL,
    sets = NULL, duplicates.in.same.set = TRUE, re.estimate = TRUE,
    param = object[["variogram.object"]][[1]][["param"]],
    fit.param = object[["variogram.object"]][[1]][["fit.param"]],
    aniso = object[["variogram.object"]][[1]][["aniso"]],
    fit.aniso = object[["variogram.object"]][[1]][["fit.aniso"]],
    variogram.object = NULL,
    use.fitted.param = TRUE, return.fit = FALSE,
    reduced.output = TRUE, lgn = FALSE,
    mfl.action = c("offset", "stop"),
    ncores = min(nset, detectCores()), verbose = 0, ...)
```

Arguments

object an object of class of "georob", see georob0bject.

formula an optional formula for the regression model passed by update to georob.

subset an optional vector specifying a subset of observations to be used in the fitting

process.

method keyword, controlling whether subsets are formed by partitioning data set into

blocks by kmeans (default) or randomly. Ignored if sets is non-NULL.

nset positive integer defining the number <math>K of subsets into which the data set is

partitioned (default: nset = 10). Ignored if sets is non-NULL.

seed optional integer seed to initialize random number generation, see set.seed.

Ignored if sets is non-NULL.

sets an optional vector of the same length as the response vector of the fitted model

and with positive integers taking values in $(1, 2, \dots, K)$, defining in this way the K subsets into which the data set is split. If sets = NULL (default) the partition

is randomly generated by kmeans or runif (using possibly seed).

duplicates.in.same.set

logical controlling whether replicated observations at a given location are as-

signed to the same subset when partitioning the data (default TRUE).

re.estimate logical controlling whether the model is re-fitted to the reduced data sets before

computing the Kriging predictions (TRUE, default) or whether the model passed in object is used to compute the predictions for the omitted observations, see

Details.

param a named numeric vector or a matrix or data frame with initial values of vari-

ogram parameters passed by update to georob. If param is a matrix (or a data

frame) then it must have nset rows and

length(object[["variogram.object"]][[1]][["param"]]) columns with initial values of variogram parameters for the nset cross-validation sets, and

colnames(param) must match

names(object[["variogram.object"]][[1]][["param"]]).

fit.param a named logical vector or a matrix or data frame defining which variogram pa-

rameters should be adjusted by update. If fit.param is a matrix (or a data

frame) then it must have nset rows and

length(object[["variogram.object"]][[1]][["fit.param"]]) columns
with variogram parameter fitting flags for the nset cross-validation sets, and

colnames(param) must match

names(object[["variogram.object"]][[1]][["fit.param"]]).

aniso a named numeric vector or a matrix or data frame with initial values of anisotropy

parameters passed by update to georob. If aniso is a matrix (or a data frame)

then it must have nset rows and

length(object[["variogram.object"]][[1]][["aniso"]]) columns with
initial values of anisotropy parameters for the nset cross-validation sets, and

colnames(aniso) must match

names(object[["variogram.object"]][[1]][["aniso"]]).

fit.aniso a named logical vector or a matrix or data frame defining which anisotropy pa-

rameters should be adjusted by update. If fit.aniso is a matrix (or a data

frame) then it must have nset rows and length(object[["variogram.object"]][[1]][["fit.aniso"]]) columns with anisotropy parameter fitting flags for the nset cross-validation sets, and colnames(param) must match names(object[["variogram.object"]][[1]][["fit.aniso"]]).

variogram.object

an optional list that gives initial values of for fitting a possibly nested variogram model for the cross-validation sets. Each component is a list with the following components:

- param: an optional named numeric vector or a matrix or data frame with initial values of variogram parameters passed by update to georob. If param is a matrix (or a data frame) then it must have nset rows and length(object[["variogram.object"]][[i]][["param"]]) columns with initial values of variogram parameters for the nset cross-validation sets (*i* is the *i*th variogram structure), and colnames(param) must match names(object[["variogram.object"]][[i]][["param"]]).
- fit.param: an optional named logical vector or a matrix or data frame defining which variogram parameters should be adjusted by update. If fit.param is a matrix (or a data frame) then it must have nset rows and length(object[["variogram.object"]][[i]][["fit.param"]]) columns with variogram parameter fitting flags for the nset cross-validation sets (i is the ith variogram structure), and colnames(param) must match names(object[["variogram.object"]][[i]][["fit.param"]]).
- aniso: an optional named numeric vector or a matrix or data frame with initial values of anisotropy parameters passed by update to georob. If aniso is a matrix (or a data frame) then it must have nset rows and length(object[["variogram.object"]][[i]][["aniso"]]) columns with initial values of anisotropy parameters for the nset cross-validation sets (*i* is the *i*th variogram structure), and colnames(aniso) must match names(object[["variogram.object"]][[i]][["aniso"]]).
- fit.aniso: an optional named logical vector or a matrix or data frame defining which anisotropy parameters should be adjusted by update. If fit.aniso is a matrix (or a data frame) then it must have nset rows and length(object[["variogram.object"]][[i]][["fit.aniso"]]) columns with anisotropy parameter fitting flags for the nset cross-validation sets(i is the ith variogram structure), and colnames(param) must match names(object[["variogram.object"]][[i]][["fit.aniso"]]).

use.fitted.param

logical scalar controlling whether fitted values of param (and aniso are used as initial values when variogram parameters are fitted for the cross-validation sets (default TRUE).

return.fit logical controlling whether information about the fit should be returned when re-estimating the model with the reduced data sets (default FALSE).

reduced.output logical controlling whether the complete fitted model objects, fitted to the reduced data sets, are returned (FALSE) or only some components (TRUE, default, see *Value*). Ignored if return.fit = FALSE.

lgn logical controlling whether Kriging predictions of a log-transformed response

should be transformed back to the original scale of the measurements (default

FALSE).

mfl.action character controlling what is done when some levels of factor(s) are not present

in any of the subsets used to fit the model. The function either stops ("stop")

or treats the respective factors as model offset ("offset", default).

ncores positive integer controlling how many cores are used for parallelized computa-

tions, see Details.

verbose positive integer controlling logging of diagnostic messages to the console during

model fitting. Passed by update to georob.

additional arguments passed by update to georob, see *Details*.

Details

Note that the data frame passed as data argument to georob must exist in the user workspace when calling cv.georob.

cv.georob then uses the packages **parallel**, **snow** and **snowfall** for parallelized computations. By default, the function uses K CPUs but not more than are physically available (as returned by detectCores).

cv.georob uses the function update to re-estimated the model with the reduced data sets. Therefore, any argument accepted by georob except data can be changed when re-fitting the model. Some of them (e.g. formula, subset, etc.) are explicit arguments of cv.georob, but also the remaining ones can be passed by . . . to the function.

Practitioners in geostatistics commonly cross-validate a fitted model without re-estimating the model parameters with the reduced data sets. This is clearly an unsound practice (see Hastie et al., 2009, sec. 7.10). Therefore, the argument re.estimate should always be set to TRUE. The alternative is provided only for historic reasons.

Value

An object of class cv. georob, which is a list with the two components pred and fit.

pred is a data frame with the coordinates and the cross-validation prediction results with the following variables:

subset an integer vector defining to which of the K subsets an observation was as-

signed.

data the values of the (possibly log-transformed) response.

pred the Kriging predictions. se the Kriging standard errors.

If 1gn = TRUE then pred has the additional variables:

lgn.data the untransformed response.

lgn.pred the unbiased back-transformed predictions of a log-transformed response.

lgn. se the Kriging standard errors of the back-transformed predictions of a

log-transformed response.

The second component fit contains either the full outputs of georob, fitted for the K reduced data sets (reduced.output = FALSE), or K lists with the components tuning.psi, converged, convergence.code, gradient, variogram.object, coefficients along with the standard errors of $\widehat{\beta}$, see georob0bject.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Hastie, T., Tibshirani, R. and Friedman, J. (2009) *The Elements of Statistical Learning; Data Mining, Inference and Prediction*. New York: Springer-Verlag.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; georobObject for a description of the class georob; profilelogLik for computing profiles of Gaussian likelihoods; plot.georob for display of RE(ML) variogram estimates; control.georob for controlling the behaviour of georob; georobModelBuilding for stepwise building models of class georob; georobMethods for further methods for the class georob; predict.georob for computing robust Kriging predictions; validate.predictions for validating Kriging predictions; lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data; georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

Examples

```
## Not run:
data(meuse)

r.logzn <- georob(log(zinc) ~ sqrt(dist), data = meuse, locations = ~ x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1)

r.logzn.cv.1 <- cv(r.logzn, seed = 1, lgn = TRUE, ncores = 1, verbose = 1)
## using multiple cores
## r.logzn.cv.1 <- cv(r.logzn, seed = 1, lgn = TRUE)
r.logzn.cv.2 <- cv(r.logzn, formula = .~. + ffreq, seed = 1, lgn = TRUE,</pre>
```

default.aniso 15

```
ncores = 1, verbose = 1)
## using multiple cores
## r.logzn.cv.2 <- cv(r.logzn, formula = .~. + ffreq, seed = 1, lgn = TRUE,
## ncores = 1, verbose = 1)

plot(r.logzn.cv.1, type = "bs")
plot(r.logzn.cv.2, type = "bs", add = TRUE, col = "red")

legend("topright", lty = 1, col = c("black", "red"), bty = "n",
    legend = c("log(Zn) ~ sqrt(dist)", "log(Zn) ~ sqrt(dist) + ffreq"))
## End(Not run)</pre>
```

default.aniso

Setting Default Values of Variogram Parameters

Description

Helper functions to set sensible default values for anisotropy parameters and for controlling what variogram and anisotropy parameters should be estimated.

Usage

```
default.aniso(f1 = 1., f2 = 1., omega = 90., phi = 90., zeta = 0.)

default.fit.param(
  variance = TRUE, snugget = FALSE, nugget = TRUE, scale = TRUE,
  alpha = FALSE, beta = FALSE, delta = FALSE, gamma = FALSE,
  kappa = FALSE, lambda = FALSE, mu = FALSE, nu = FALSE)

default.fit.aniso(f1 = FALSE, f2 = FALSE, omega = FALSE,
  phi = FALSE, zeta = FALSE)
```

Arguments

variance	variance (sill σ^2) of the auto-correlated component of the Gaussian random field $B(s)$.	
snugget	variance (spatial nugget σ_n^2) of the seemingly spatially uncorrelated component of $B(s)$ (micro-scale spatial variation; default value snugget = \emptyset).	
nugget	variance (nugget τ^2) of the independent errors $\varepsilon(s)$.	
scale	range parameter (α) of the variogram.	
alpha, beta, delta, gamma, kappa, lambda, mu, nu		
	names of additional variogram parameters such as the smoothness parameter ν of the Whittle-Mat\'ern model (see RMmodel and param.names).	
f1	positive ratio f_1 of lengths of second and first semi-principal axes of an ellipsoidal surface with constant semi-variance in \mathbb{R}^3 (default f1 = 1).	

16 elevation

f2	positive ratio f_2 of lengths of third and first semi-principal axes of the semi-variance ellipsoid (default f2 = 1).
omega	azimuth in degrees of the first semi-principal axis of the semi-variance ellipsoid (default omega = 90).
phi	90 degrees minus altitude of the first semi-principal axis of the semi-variance ellipsoid (default phi = 90).
zeta	angle in degrees between the second semi-principal axis and the direction of the line defined by the intersection between the x - y -plane and the plane orthogonal to the first semi-principal axis of the semi-variance ellipsoid through the origin (default zeta = 0).

Value

Either a named numeric with initial values of anisotropy parameters (default.aniso) or named logical vector, controlling what parameters should be estimated (default.fit.param, default.fit.aniso).

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models.
```

Examples

```
default.aniso(f1 = 0.5, omega = 45)
default.fit.param(scale=FALSE, alpha = TRUE)
default.fit.aniso(f1 = TRUE, omega = TRUE)
```

elevation

Elevation Data

Description

Surface elevation data taken from Davis (1972).

Usage

```
data(elevation)
```

Format

A data frame with 52 observations on the following 3 variables:

x a numeric vector with the easting coordinate in multiplies of 50 feet.

y a numeric vector with the northing coordinate in multiplies of 50 feet..

height a numeric vector with the elevation in multiples of 10 feet.

Note

The data were imported from the package **geoR**.

Source

Davis, J.C. (1973) Statistics and Data Analysis in Geology. New York: Wiley.

Examples

```
data(elevation)
summary(elevation)
```

fit.variogram.model

Fitting Model Functions to Sample Variograms

Description

The function fit.variogram.model fits a variogram model to a sample variogram by (weighted) non-linear least squares. There are print, summary and lines methods for summarizing and displaying fitted variogram models.

Usage

```
fit.variogram.model(sv,
    variogram.model = c("RMexp", "RMaskey", "RMbessel", "RMcauchy",
        "RMcircular", "RMcubic", "RMdagum", "RMdampedcos", "RMdewijsian",
        "RMfbm", "RMgauss", "RMgencauchy", "RMgenfbm", "RMgengneiting",
        "RMgneiting", "RMlgd", "RMmatern", "RMpenta", "RMqexp",
        "RMspheric", "RMstable", "RMwave", "RMwhittle"),
    param, fit.param = default.fit.param()[names(param)],
    aniso = default.aniso(), fit.aniso = default.fit.aniso(),
        variogram.object = NULL,
        max.lag = max(sv[["lag.dist"]]), min.npairs = 30,
        weighting.method = c("cressie", "equal", "npairs"),
        control = control.fit.variogram.model(),
        verbose = 0)

control.fit.variogram.model(maximizer = c("nlminb", "optim"),
        param.tf = param.transf(), fwd.tf = fwd.transf(),
```

```
deriv.fwd.tf = dfwd.transf(), bwd.tf = bwd.transf(),
   hessian = TRUE, optim = control.optim(), nlminb = control.nlminb())
## S3 method for class 'fitted.variogram'
print(x, digits = max(3, getOption("digits") - 3), ...)
## S3 method for class 'fitted.variogram'
summary(object, correlation = FALSE, signif = 0.95, ...)
## S3 method for class 'fitted.variogram'
lines(x, what = c("variogram", "covariance", "correlation"),
    from = 1.e-6, to, n = 501, xy.angle = 90, xz.angle = 90,
   col = 1:length(xy.angle), pch = 1:length(xz.angle), lty = "solid", ...)
```

Arguments

s۷ an object of class sample.variogram, see sample.variogram. variogram.model

> a character keyword defining the variogram model to be fitted. Currently, most basic variogram models provided by the package RandomFields can be fitted (see *Details* of georob and RMmodel).

param

a named numeric vector with initial values of the variogram parameters. The following parameter names are allowed (see *Details* of georob and georobIntro for information about the parametrization of variogram models):

- variance: variance (sill σ^2) of the auto-correlated component of the Gaussian random field B(s).
- snugget: variance (spatial nugget σ_n^2) of the seemingly spatially uncorrelated component of B(s) (micro-scale spatial variation; default value snugget = 0).
- nugget: variance (nugget τ^2) of the independent errors $\varepsilon(s)$.
- scale: range parameter (α) of the variogram.
- · names of additional variogram parameters such as the smoothness parameter ν of the Whittle-Mat\'ern model (see RMmodel and param.names).

fit.param

a named logical vector (or a function such as default.fit.param that creates this vector) with the same names as used for param, defining which parameters are adjusted (TRUE) and which are kept fixed at their initial values (FALSE) when fitting the model.

aniso

a named numeric vector with initial values (or a function such as default.aniso that creates this vector) for fitting geometrically anisotropic variogram models. The names of aniso are matched against the following names (see Details and georobIntro for information about the parametrization of variogram models):

- f1: ratio f_1 of lengths of second and first semi-principal axes of an ellipsoidal surface with constant semi-variance in \mathbb{R}^3 (default f1 = 1).
- f2: ratio f_2 of lengths of third and first semi-principal axes of the semivariance ellipsoid (default f2 = 1).

- omega: azimuth in degrees of the first semi-principal axis of the semi-variance ellipsoid (default omega = 90).
- phi: 90 degrees minus altitude of the first semi-principal axis of the semi-variance ellipsoid (default phi = 90).
- zeta: angle in degrees between the second semi-principal axis and the direction of the line defined by the intersection between the x-y-plane and the plane orthogonal to the first semi-principal axis of the semi-variance ellipsoid through the origin (default zeta = 0).

fit.aniso

a named logical vector (or a function such as default.fit.aniso that creates this vector) with the same names as used for aniso, defining which parameters are adjusted (TRUE) and which are kept fixed at their initial values (FALSE) when fitting the model.

variogram.object

an optional list that defines a possibly nested variogram model. Each component is itself a list with the following components:

- variogram.model: a character keyword defining the variogram model, see respective argument above.
- param: a named numeric vector with initial values of the variogram parameters, see respective argument above.
- fit.param: a named logical vector defining which parameters are adjusted, see respective argument above.
- aniso: a named numeric vector with initial values for fitting geometrically anisotropic variogram models, see respective argument above.
- fit.param: a named logical vector defining which anisotropy parameters are adjusted, see respective argument above.

Note that the arguments variogram.model, param, fit.param, aniso and fit.aniso are ignored when variogram.object is passed to fit.variogram.model.

max.lag

a positive numeric defining the maximum lag distance to be used for fitting or plotting variogram models (default all lag classes).

min.npairs

a positive integer defining the minimum number of data pairs required so that a lag class is used for fitting a variogram model (default 30).

weighting.method

a character keyword defining the weights for non-linear least squares. Possible values are:

- "equal": no weighting,
- "npairs": weighting by number of data pairs in a lag class,
- "cressie": "Cressie's weights" (default, see Cressie, 1993, sec. 2.6.2).

verbose

positive integer controlling logging of diagnostic messages to the console during model fitting.

control

a list with the components maximizer, param.tf, fwd.tf, bwd.tf, hessian, optim and nlminb or a function such as control.fit.variogram.model that generates such a list. See codecontrol.georob for information on codemaximizer, param.tf, fwd.tf, bwd.tf, hessian, optim and nlminb.

maximizer	character keyword defining the optimizer for nonlinear least squares. Possible values are nlminb (default) or optim.
hessian	logical scalar controlling whether the Hessian should be computed at the non-linear least squares estimates.
param.tf	a function such as param.transf, which returns a named vector of character strings that define the transformations to be applied to the variogram parameters for model fitting, see control.georob.
fwd.tf	a function such as fwd.transf, which returns a named list of invertible functions to be used to transform variogram parameters, see control.georob.
deriv.fwd.tf	a function such as dfwd.transf, which returns a named list of functions corresponding to the first derivatives of fwd.tf, see <i>Details</i> .
bwd.tf	a function such as <pre>bwd.transf</pre> , which returns the named list of inverse functions corresponding to <pre>fwd.tf</pre> , see see <pre>control.georob</pre> .
nlminb	a list of arguments passed to nlminb or a function such as control.nlminb that generates such a list (see nlminb for allowed arguments).
optim	a list of arguments passed to optim or a function such as control.optim that generates such a list (see optim for allowed arguments).
object, x	an object of class fitted.variogram.
digits	positive integer indicating the number of decimal digits to print.
correlation	logical controlling whether the correlation matrix of the fitted variogram parameters is computed (default FALSE).
signif	confidence level for computing confidence intervals for variogram parameters (default \emptyset . 95).
what	the quantity that should be displayed (default "variogram").
from	numeric, minimal lag distance used in plotting variogram models.
to	numeric, maximum lag distance used in plotting variogram models (default: largest lag distance of current plot).
n	positive integer specifying the number of equally spaced lag distances for which semi-variances are evaluated in plotting variogram models (default 501).
xy.angle	numeric (vector) with azimuth angles (in degrees, clockwise positive from north) in x - y -plane for which semi-variances should be plotted.
xz.angle	numeric (vector) with angles in x - z -plane (in degrees, clockwise positive from zenith to south) for which semi-variances should be plotted.
col	color of curves to distinguish curves relating to different azimuth angles in x - y -plane.
pch	type of plotting symbols added to lines to distinguish curves relating to different angles in x - z -plane.
lty	line type for plotting variogram models.
	additional arguments passed to methods.

Details

The parametrization of geometrically anisotropic variograms is described in detail in georobIntro, and the section *Details* of georob describes how the parameter estimates are constrained to permissible ranges. The same mechanisms are used in fit.variogram.model.

The method summary computes confidence intervals of the estimated variogram and anisotropy parameters from the Hessian matrix of the residual sums of squares, based on the asymptotic normal distribution of least squares estimate estimates. Note that the Hessian matrix with respect to the *transformed* variogram and anisotropy parameters is used for this. Hence the inverse Hessian matrix is the covariance matrix of the transformed parameters, confidence intervals are first computed for the transformed parameters and the limits of these intervals are transformed back to the original scale of the parameters. Optionally, summary reports the correlation matrix of the *transformed* parameters, also computed from the Hessian matrix.

Value

The function fit.variogram.model generates an object of class fitted.variogram which is a list with the following components:

sse the value of the object function (weighted residual sum of squares) evaluated at the solution.

variogram.object

the estimated parameters of a possibly nested variograms model. This is a list that contains for each variogram model structure the following components:

- variogram.model: the name of the fitted parametric variogram model.
- param: a named numeric vector with the (estimated) variogram parameters.
- fit.param: a named logical vector with the flags defining what variogram parameters were estimated.
- isotropic: logical indicating whether an isotropic variogram was fitted.
- aniso: a named numeric vector with the (estimated) anisotropy parameters.
- fit.aniso: a named logical vector with the flags defining what anisotropy parameters were estimated.
- sincos: a list with sin and cos of the angles ω , ϕ and ζ that define the orientation of the anisotropy ellipsoid.
- rotmat: the matrix (C_1, C_2, C_3) (see georobIntro).
- sclmat: a vector with the elements 1, $1/f_1$, $1/f_2$ (see georobIntro).

param.tf a character vector listing the transformations of the variogram parameters used for model fitting.

fwd.tf a list of functions for variogram parameter transformations.

bwd.tf a list of functions for *inverse* variogram parameter transformations.

converged logical indicating whether numerical maximization by optim converged.

convergence.code

a diagnostic integer issued by optim (component convergence) about convergence.

a named integer vector of length two with the number of function and gradient evaluations by optim.

iter

call the matched call.

residuals a numeric vector with the residuals, that is the sample semi-variance minus the

fitted values.

fitted a numeric vector with the modelled semi-variances. weights a numeric vector with the weights used for fitting.

hessian a symmetric matrix with the Hessian at the solution (missing if hessian is false).

hessian.tfpa a symmetric matrix with the Hessian at the solution with respect to the trans-

formed variogram and anisotropy parameters (missing if hessian is false). This Hessian is used by summary.fitted.variogram to compute confidence inter-

vals for the estimated parameters.

hessian.ntfpa a symmetric matrix with the Hessian at the solution with respect to the non-

transformed variogram and anisotropy parameters (missing if hessian is false).

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Cressie, N. A. C. (1993) Statistics for Spatial Data. New York: John Wiley & Sons.

See Also

georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models;
georobObject for a description of the class georob;
profilelogLik for computing profiles of Gaussian likelihoods;
plot.georob for display of RE(ML) variogram estimates;
control.georob for controlling the behaviour of georob;
georobModelBuilding for stepwise building models of class georob;
cv.georob for assessing the goodness of a fit by georob;
georobMethods for further methods for the class georob;
predict.georob for computing robust Kriging predictions;
lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data;

georobSimulation for simulating realizations of a Gaussian process from model fitted by georob.

Examples

```
data(wolfcamp)
## fitting an isotropic IRF(0) model
r.sv.iso <- sample.variogram(pressure~1, data = wolfcamp,
    locations = ~x + y, lag.dist.def = seq(0, 200, by = 15))
## Not run:</pre>
```

```
r.irf0.iso <- fit.variogram.model(r.sv.iso, variogram.model = "RMfbm",</pre>
    param = c(variance = 100, nugget = 1000, scale = 1., alpha = 1.),
    fit.param = default.fit.param(scale = FALSE, alpha = TRUE))
summary(r.irf0.iso, correlation = TRUE)
plot(r.sv.iso, type = "l")
lines(r.irf0.iso, line.col = "red")
## End(Not run)
## fitting an anisotropic IRF(0) model
r.sv.aniso <- sample.variogram(pressure~1, data = wolfcamp,</pre>
    locations = ^{x} + y, lag.dist.def = seq(0, 200, by = 15),
    xy.angle.def = c(0., 22.5, 67.5, 112.5, 157.5, 180.))
## Not run:
r.irf0.aniso <- fit.variogram.model(r.sv.aniso, variogram.model = "RMfbm",</pre>
   param = c(variance = 100, nugget = 1000, scale = 1., alpha = 1.5),
   fit.param = default.fit.param(scale = FALSE, alpha = TRUE),
   aniso = default.aniso(f1 = 0.4, omega = 135.),
   fit.aniso = default.fit.aniso(f1 = TRUE, omega = TRUE),
    control = control.fit.variogram.model(
      maximizer = "optim",
      optim = control.optim(
        method = "BFGS", hessian = TRUE, control = list(maxit = 5000)
   ))
summary(r.irf0.aniso, correlation = TRUE)
plot(r.sv.aniso, type = "l")
lines(r.irf0.aniso, xy.angle = seq(0, 135, by = 45))
## End(Not run)
```

georob

Robust Fitting of Spatial Linear Models

Description

The function georob fits a linear model with spatially correlated errors to geostatistical data that are possibly contaminated by independent outliers. The regression coefficients and the parameters of the variogram model are estimated by robust or Gaussian restricted maximum likelihood (REML) or by Gaussian maximum likelihood (ML).

Usage

```
"RMgneiting", "RMlgd", "RMmatern", "RMpenta", "RMqexp",
      "RMspheric", "RMstable", "RMwave", "RMwhittle"),
 param, fit.param = default.fit.param()[names(param)],
aniso = default.aniso(), fit.aniso = default.fit.aniso(),
 variogram.object = NULL,
 tuning.psi = 2, control = control.georob(),
 verbose = 0, ...)
```

Arguments

formula a symbolic description of the regression model for the external drift to be fit

(mandatory argument). See 1m and formula for more details.

data an optional data frame, a SpatialPointsDataFrame, list or environment (or an-

> other object coercible by as.data.frame to a data frame) containing the variables in the model and the coordinates where the data was recorded. If not found in data, the variables are taken from environment (formula), typically

the environment from which georob is called.

subset an optional vector specifying a subset of observations to be used in the fitting

process.

weights an optional vector of weights to be used in the fitting process, currently ignored.

na.action a function which indicates what should happen when the data contain NAs. The

default is set by the na. action argument of options, and is na. fail if that is unset. The "factory-fresh" default is na.omit. Another possible value is NULL,

no action. Value na. exclude can be useful.

logicals. If TRUE the corresponding components of the fit (the model frame, the

model matrix, the response) are returned. The model frame is augmented by the

coordinates.

contrasts an optional list. See the contrasts.arg of model.matrix.default.

offset this optional argument can be used to specify an a priori known component to be included in the linear predictor during fitting. An offset term can be included

in the formula instead or as well, and if both are specified their sum is used.

locations a one-sided formula defining the variables that are used as coordinates of the locations were the data was recorded (mandatory argument).

variogram.model

a character keyword defining the variogram model to be fitted. Currently, most basic variogram models provided by the package RandomFields can be fitted

(see *Details* and RMmodel).

a named numeric vector with initial values of the variogram parameters (mandatory argument). The names of param are matched against the following names (see Details and georobIntro for information about the parametrization of variogram models):

- variance: variance (sill σ^2) of the auto-correlated component of the Gaussian random field B(s).
- snugget: variance (spatial nugget σ_n^2) of the seemingly spatially uncorrelated component of B(s) (micro-scale spatial variation; default value snugget = 0).

model, x, y

param

- nugget: variance (nugget τ^2) of the independent errors $\varepsilon(s)$.
- scale: range parameter (α) of the variogram.
- names of additional variogram parameters such as the smoothness parameter ν of the Whittle-Mat\'ern model (see RMmodel and param.names).

fit.param

a named logical vector (or a function such as default.fit.param that creates this vector) with the same names as used for param, defining which parameters are adjusted (TRUE) and which are kept fixed at their initial values (FALSE) when fitting the model.

aniso

a named numeric vector with initial values (or a function such as default.aniso that creates this vector) for fitting geometrically anisotropic variogram models. The names of aniso are matched against the following names (see *Details* and georobIntro for information about the parametrization of variogram models):

- f1: ratio f_1 of lengths of second and first semi-principal axes of an ellipsoidal surface with constant semi-variance in \mathbb{R}^3 (default f1 = 1).
- f2: ratio f_2 of lengths of third and first semi-principal axes of the semi-variance ellipsoid (default f2 = 1).
- omega: azimuth in degrees of the first semi-principal axis of the semi-variance ellipsoid (default omega = 90).
- phi: 90 degrees minus altitude of the first semi-principal axis of the semi-variance ellipsoid (default phi = 90).
- zeta: angle in degrees between the second semi-principal axis and the direction of the line defined by the intersection between the x-y-plane and the plane orthogonal to the first semi-principal axis of the semi-variance ellipsoid through the origin (default zeta = 0).

fit.aniso

a named logical vector (or a function such as default.fit.aniso that creates this vector) with the same names as used for aniso, defining which parameters are adjusted (TRUE) and which are kept fixed at their initial values (FALSE) when fitting the model.

variogram.object

an optional list that defines a possibly nested variogram model. Each component is itself a list with the following components:

- variogram.model: a mandatory character keyword defining the variogram model, see respective argument above.
- param: a mandatory named numeric vector with initial values of the variogram parameters, see respective argument above.
- fit.param: an optional named logical vector defining which parameters are adjusted, see respective argument above.
- aniso: an optional named numeric vector with initial values for fitting geometrically anisotropic variogram models, see respective argument above.
- fit.param: an optional named logical vector defining which anisotropy parameters are adjusted, see respective argument above.

Note that the arguments variogram.model, param, fit.param, aniso and fit.aniso are ignored when variogram.object is passed to georob.

tuning.psi

positive numeric. The tuning constant c of the ψ_c -function of the robust REML algorithm.

control a list specifying parameters that control the behaviour of georob. Use the function control georob and see its help page for the components of control.

verbose positive integer controlling logging of diagnostic messages to the console during

model fitting. verbose = 0 largely suppresses such messages and verbose = 4 asks for most verbose output (see control arguments of nleqslv, nlminb and optim and control.georob for information how to fine tuning diagnostic

output generated by nleqslv, nlminb and optim).

further arguments passed to function (e.g. object. used internally for updating

georob objects).

Details

georob fits a spatial linear model by robust or Gaussian RE(ML) (Künsch et al., 2011, Künsch et al., in preparation). georobIntro describes the employed model and briefly sketches the robust REML estimation and the robust external drift Kriging method. Here, we describe further details of georob.

Implemented variograms:

Currently, most basic variogram models provided by the package **RandomFields** can be fitted by georob (see argument variogram.model for a list of implemented models). Some of these models have in addition to variance, snugget, nugget and scale further parameters. Initial values of these parameters (param) and fitting flags (fit.param) must be passed to georob by the same names as used by the functions RM... of the package **RandomFields** (see RMmodel). Use the function param.names to list additional parameters of a given variogram.model.

The arguments fit.param and fit.aniso are used to control what variogram and anisotropy parameters are estimated and which are kept at the constant initial values. The functions default.fit.param and default.fit.aniso set reasonable default values for these arguments. Note, as an aside, that the function default.aniso sets (default) values of the anisotropy parameters for an isotropic variogram.

Estimating parameters of power function variogram:

The intrinsic variogram model RMfbm is over-parametrized when both the variance (plus possibly snugget) and the scale are estimated. Therefore, to estimate the parameters of this model, scale must be kept fixed at an arbitrary value by using fit.param["scale"] = FALSE.

Estimating parameters of geometrically anisotropic variograms:

The subsection **Model** of georobIntro describes how such models are parametrized and gives definitions the various elements of aniso. Some additional remarks might be helpful:

- The first semi-principal axis points into the direction with the farthest reaching auto-correlation, which is described by the range parameter scale (α) .
- The ranges in the direction of the second and third semi-principal axes are given by $f_1\alpha$ and $f_2\alpha$, with $0 < f_2 \le f_1 \le 1$.
- The default values for an iso $(f_1 = 1, f_2 = 1)$ define an isotropic variogram model.
- Valid ranges for the angles characterizing the orientation of the semi-variance ellipsoid are (in degrees): ω [0, 180], ϕ [0, 180], ζ [-90, 90].

Estimating variance of micro-scale variation:

Simultaneous estimation of the variance of the micro-scale variation (snugget, $\sigma_{\rm n}^2$), appears seemingly as spatially uncorrelated with a given sampling design, and of the variance (nugget, τ^2) of the independent errors requires that for some locations s_i replicated observations are available. Locations less or equal than zero.dist apart are thereby considered as being coincident (see control.georob).

Constraining estimates of variogram parameters:

Parameters of variogram models can vary only within certain bounds (see param.bounds and RMmodel for allowed ranges). georob uses three mechanisms to constrain parameter estimates to permissible ranges:

- 1. *Parameter transformations*: By default, all variance (variance, snugget, nugget), the range scale, the anisotropy parameters f1 and f2 and many of the additional parameters are log-transformed before solving the estimating equations or maximizing the restricted log-likelihood and this warrants that the estimates are always positive (see control.georob for detailed explanations how to control parameter transformations).
- 2. Checking permissible ranges: The additional parameters of the variogram models such as the smoothness parameter ν of the Whittle-Mat\'ern model are forced to stay in the permissible ranges by signalling an error to nleqslv, nlminb or optim if the current trial values are invalid. These functions then graciously update the trial values of the parameters and carry their task on. However, it is clear that such a procedure likely gets stuck at a point on the boundary of the parameter space and is therefore just a workaround for avoiding runtime errors due to invalid parameter values.
- 3. Exploiting the functionality of nlminb and optim: If a spatial model is fitted non-robustly, then the arguments lower, upper (and method of optim) can be used to constrain the parameters (see control.optim how to pass them to optim). For optim one has to use the arguments method = "L-BFGS-B", lower = 1, upper = u, where 1 and u are numeric vectors with the lower and upper bounds of the transformed parameters in the order as they appear in c(variance, snugget, nugget, scale, ...)[fit.param], aniso[fit.aniso]), where ... are additional parameters of isotropic variogram models (use param.names(variogram.model) to display the names and the order of the additional parameters for variogram.model). For nlminb one has to use the arguments codelower = 1, upper = u, where 1 and u are numeric vectors as described above.

Computing robust initial estimates of parameters for robust REML:

To solve the robustified estimating equations for B and β the following initial estimates are used:

- $\widehat{B} = 0$, if this turns out to be infeasible, initial values can be passed to georob by the argument bhat of control.georob.
- β is either estimated robustly by the function lmrob, rq or non-robustly by lm (see argument initial.fixef of control.georob).

Finding the roots of the robustified estimating equations of the variogram and anisotropy parameters is more sensitive to a good choice of initial values than maximizing the Gaussian (restricted) log-likelihood with respect to the same parameters. If the initial values for param and aniso are not sufficiently close to the roots of the system of nonlinear equations, then nleqslv may fail to find them. Setting initial.param = TRUE (see control.georob) allows one to find initial values that are often sufficiently close to the roots so that nleqslv converges. This is achieved by:

1. Initial values of the regression parameters are computed by lmrob irrespective of the choice for initial.fixef (see control.georob).

- 2. Observations with "robustness weights" of the 1mrob fit, satisfying $\psi_c(\widehat{\varepsilon}_i/\widehat{\tau})/(\widehat{\varepsilon}_i/\widehat{\tau}) \leq \min$ rweight, are discarded (see control.georob).
- 3. The model is fit to the pruned data set by Gaussian REML using nlminb or optim.
- 4. The resulting estimates of the variogram parameters (param, aniso) are used as initial estimates for the subsequent robust fit of the model by nleqslv.

Note that for step 3 above, initial values of param and aniso must be provided to georob.

Estimating variance parameters by Gaussian (RE)ML:

Unlike robust REML, where robustified estimating equations are solved for the variance parameters nugget (τ^2) , variance (σ^2) , and possibly snugget (σ_n^2) , for Gaussian (RE)ML the variances can be re-parametrized to

- the signal variance $\sigma_B^2 = \sigma^2 + \sigma_{\rm n}^2$,
- the inverse relative nugget $\eta = \sigma_B^2/\tau^2$ and
- the relative auto-correlated signal variance $\xi = \sigma^2/\sigma_B^2$.

georob maximizes then a (restricted) profile log-likelihood that depends only on η , ξ , α , ..., and σ_B^2 is estimated by an explicit expression that depends on these parameters (e.g. Diggle and Ribeiro, 2006, p. 113). This is usually more efficient than maximizing the (restricted) log-likelihood with respect to the original variance parameters τ^2 , σ_n^2 and σ^2 . georob chooses the parametrization automatically, but the user can control it by the argument reparam of the function control georob.

Value

An object of class georob representing a robust (or Gaussian) (RE)ML fit of a spatial linear model. See georobObject for the components of the fit.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch> with contributions by Cornelia Schwierz.

References

Diggle, P. J. and Ribeiro, P. J. R. (2006) Model-based Geostatistics. Springer.

Künsch, H. R., Papritz, A., Schwierz, C. and Stahel, W. A. (in preparation) Robust Geostatistics.

Künsch, H. R., Papritz, A., Schwierz, C. and Stahel, W. A. (2011) Robust estimation of the external drift and the variogram of spatial data. Proceedings of the ISI 58th World Statistics Congress of the International Statistical Institute. doi: 10.3929/ethza009900710

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georobObject for a description of the class georob; profilelogLik for computing profiles of Gaussian likelihoods;
```

```
plot.georob for display of RE(ML) variogram estimates;
control.georob for controlling the behaviour of georob;
georobModelBuilding for stepwise building models of class georob;
cv.georob for assessing the goodness of a fit by georob;
georobMethods for further methods for the class georob;
predict.georob for computing robust Kriging predictions;
lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data;
georobSimulation for simulating realizations of a Gaussian process from model fitted by georob;
and finally
sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

Examples

```
## Not run:
## meuse data ##
#################
data(meuse)
## Gaussian REML fit
r.logzn.reml <- georob(log(zinc) \sim sqrt(dist), data = meuse, locations = \sim x + y,
   variogram.model = "RMexp",
   param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1000)
summary(r.logzn.reml, correlation = TRUE)
## robust REML fit
r.logzn.rob <- update(r.logzn.reml, tuning.psi = 1)</pre>
summary(r.logzn.rob, correlation = TRUE)
plot(r.logzn.reml, lag.dist.def = seq(0, 2000, by = 100))
lines(r.logzn.rob, col = "red")
######################
## wolfcamp data ##
data(wolfcamp)
## fitting isotropic IRF(0) model
r.irf0.iso <- georob(pressure ~ 1, data = wolfcamp, locations = ~ x + y,</pre>
   variogram.model = "RMfbm",
   param = c(variance = 10, nugget = 1500, scale = 1, alpha = 1.5),
   fit.param = default.fit.param(scale = FALSE, alpha = TRUE),
    tuning.psi = 1000)
```

```
summary(r.irf0.iso)
## fitting anisotropic IRF(0) model
r.irf0.aniso <- georob(pressure \sim 1, data = wolfcamp, locations = \sim x + y,
   variogram.model = "RMfbm",
   param = c(variance = 5.9, nugget = 1450, scale = 1, alpha = 1),
   fit.param = default.fit.param(scale = FALSE, alpha = TRUE),
   aniso = default.aniso(f1 = 0.51, omega = 148.),
   fit.aniso = default.fit.aniso(f1 = TRUE, omega = TRUE),
    tuning.psi = 1000)
summary(r.irf0.aniso)
plot(r.irf0.iso, lag.dist.def = seq(0, 200, by = 7.5))
plot(r.irf0.aniso, lag.dist.def = seq(0, 200, by = 7.5),
    xy.angle.def = c(0, 22.5, 67.5, 112.5, 157.5, 180.),
    add = TRUE, col = 2:5)
pchisq(2*(r.irf0.aniso[["loglik"]] - r.irf0.iso[["loglik"]]), 2, lower = FALSE)
## End(Not run)
```

Description

georobModelBuilding

georob

This page documents the methods deviance, logLik, extractAIC, add1, drop1, step and waldtest for the class georob. The package georob provides a generic step function and a default method which is identical with the (non-generic) function step.

S3 Methods for Stepwise Building Fixed-Effects Models for Class

Usage

georobModelBuilding 31

```
drop1(object, scope, scale = 0, test = c("none", "Chisq"), k = 2,
    trace = FALSE, fixed = TRUE, use.fitted.param = TRUE, verbose = 0,
   ncores = 1, ...)
step(object, ...)
## Default S3 method:
step(object, scope, scale = 0,
   direction = c("both", "backward", "forward"), trace = 1,
   keep = NULL, steps = 1000, k = 2, ...)
## S3 method for class 'georob'
step(object, scope, scale = 0,
    direction = c("both", "backward", "forward"), trace = 1,
   keep = NULL, steps = 1000, k = 2,
   fixed.add1.drop1 = TRUE, fixed.step = fixed.add1.drop1,
   use.fitted.param = TRUE, verbose = 0, ncores = 1, ...)
## S3 method for class 'georob'
waldtest(object, ..., vcov = NULL, test = c("F", "Chisq"),
   name = NULL)
```

Arguments

object, fit an object of class georob, see georobObject.

direction the mode of stepwise search, see step.

fixed, fixed.add1.drop1

logical controlling whether the variogram parameters are not adjusted when adding or dropping model terms by add1 and drop1 (default TRUE), see De-

tails.

fixed.step logical controlling whether the variogram parameters are not adjusted after hav-

ing called add1 and drop1 in step (default TRUE), see Details.

k numeric specifying the 'weight' of the equivalent degrees of freedom (=: edf)

part in the AIC formula, see extractAIC.

keep a filter function whose input is a fitted model object and the associated AIC

statistic, and whose output is arbitrary, see step.

name a function for extracting a suitable name/description from a fitted model object.

By default the name is queried by calling formula, see waldtest.

ncores integer specifying the number of cores used for parallelized execution of add1

and drop1. If larger than one then the minimum of ncores, detectCores() and the number of terms to be added or dropped determines the number of cores that

is actually used.

REML logical controlling whether the restricted log-likelihood should be extracted (de-

fault TRUE).

scale numeric, currently not used, see extractAIC.

scope	defines the range of models examined in the stepwise search. This should be
	either a single formula, or a list containing components upper and lower, both

formulae, see step for details.

steps the maximum number of steps to be considered (default is 1000), see step.

test character keyword specifying whether to compute the large sample Chi-squared

statistic (with asymptotic Chi-squared distribution) or the finite sample F statis-

tic (with approximate F distribution), see waldtest.

trace if positive, information is printed during the running of step, see step.

use.fitted.param

logical scalar controlling whether fitted values of param (and aniso are used as initial values when variogram parameters are fitted afresh for adding and

dropping terms from the model (default TRUE).

vcov a function for estimating the covariance matrix of the regression coefficients, see

waldtest.

verbose positive integer controlling logging of diagnostic messages to the console during

model fitting, see georob (default 0).

warn logical scalar controlling whether warnings should be suppressed.

... additional arguments passed to methods (see in particular waldtest.default).

Details

For a non-robust fit the function deviance returns the residual deviance

$$(\boldsymbol{Y} - \boldsymbol{X}\widehat{\boldsymbol{\beta}})^{\mathrm{T}}(\widehat{\tau}^{2}\boldsymbol{I} + \boldsymbol{\Gamma}_{\widehat{\boldsymbol{\theta}}})^{-1}(\boldsymbol{Y} - \boldsymbol{X}\widehat{\boldsymbol{\beta}})$$

(see georobPackage for an explanation of the notation). For a robust fit the deviance is not defined. The function then computes with a warning the deviance of an equivalent Gaussian model with heteroscedastic nugget τ^2/w where w are the "robustness weights" rweights, see georob0bject.

logLik returns the the maximized (restricted) log-likelihood. For a robust fit, the log-likelihood is not defined. The function then computes the (restricted) log-likelihood of an equivalent Gaussian model with heteroscedastic nugget (see above).

The methods extractAIC, add1, drop1 and step are used for stepwise model building.

If fixed==TRUE or fixed.add1.drop1==TRUE (default) then the variogram parameters are kept fixed at the values of object. For fixed==FALSE or fixed.add1.drop1==FALSE the variogram parameters are fitted afresh for each model tested by add1 and drop1. Then either the variogram parameters in object\$initial.objects (use.fitted.param==FALSE) or the fitted parameters of object (use.fitted.param==TRUE) are used as initial values. For fixed.step==TRUE the variogram parameters are *not* fitted afresh by step after the calls to drop1 and add1 have been completed, unlike for fixed.step==FALSE where the parameters are estimated afresh for the new model that minimized AIC (BIC) in the previous step.

In addition, the functions of the R package **multcomp** can be used to test general linear hypotheses about the fixed effects of the model.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

georobModelBuilding 33

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; georobObject for a description of the class georob; profilelogLik for computing profiles of Gaussian likelihoods; plot.georob for display of RE(ML) variogram estimates; control.georob for controlling the behaviour of georob; cv.georob for assessing the goodness of a fit by georob; georobMethods for further methods for the class georob; predict.georob for computing robust Kriging predictions; lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data; georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

Examples

```
## Not run:
data(meuse)
## Gaussian REML fit
r.logzn.reml \leftarrow georob(log(zinc) \sim sqrt(dist), data = meuse, locations = \sim x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1000)
summary(r.logzn.reml, correlation = TRUE)
deviance(r.logzn.reml)
logLik(r.logzn.reml)
waldtest(r.logzn.reml, .~. + ffreq)
step(r.logzn.reml, ~ sqrt(dist) + ffreq + soil)
## robust REML fit
r.logzn.rob <- update(r.logzn.reml, tuning.psi = 1)</pre>
deviance(r.logzn.rob)
logLik(r.logzn.rob)
logLik(r.logzn.rob, REML=TRUE)
step(r.logzn.rob, ~ sqrt(dist) + ffreq + soil, fixed.step=FALSE, trace=2)
## End(Not run)
```

34 georobObject

Description

An object of class georob as returned by georob and representing a (robustly) fitted spatial linear model. Objects of this class have methods for model building (see georobModelBuilding) and cross-validation (see cv.georob), for computing (robust) Kriging predictions (see predict.georob), for plotting (see plot.georob) and for common generic functions (see georobMethods).

Value

A georob object is a list with following components:

loglik the maximized (restricted) Gaussian log-likelihood of a non-robust (RE)ML fit or NA for a robust fit if tuning.psi is less than tuning.psi.nr.

variogram.object

the estimated parameters of a possibly nested variograms model. This is a list that contains for each variogram model structure the following components:

- variogram.model: the name of the fitted parametric variogram model.
- param: a named numeric vector with the (estimated) variogram parameters.
- fit.param: a named logical vector with the flags defining what variogram parameters were estimated.
- isotropic: logical indicating whether an isotropic variogram was fitted.
- aniso: a named numeric vector with the (estimated) anisotropy parameters.
- fit.aniso: a named logical vector with the flags defining what anisotropy parameters were estimated.
- sincos: a list with sin and cos of the angles ω , ϕ and ζ that define the orientation of the anisotropy ellipsoid.
- rotmat: the matrix (C_1, C_2, C_3) (see georobIntro).
- sclmat: a vector with the elements 1, $1/f_1$, $1/f_2$ (see georobIntro).

gradient a named numeric vector with the estimating equations (robust REML) or the gradient of the maximized (restricted) log-likelihood (Gaussian (RE)ML) eval-

uated at the solution.

tuning.psi the value of the tuning constant c of the ψ_c -function.

coefficients a named vector with the estimated regression coefficients.

fitted.values a named vector with the fitted values of the external drift $X\hat{\beta}$.

bhat a named vector with the predicted spatial random effects \hat{B} at the data locations.

residuals a named vector with the residuals $\hat{\varepsilon} = Y - X \hat{\beta} - \hat{B}$.

rweights a named numeric vector with the "robustness weights" $\psi(\widehat{\varepsilon}_i/\widehat{\tau})/(\widehat{\varepsilon}_i/\widehat{\tau})$. converged logical indicating whether numerical maximization of the (restricted)

log-likelihood by nlminb or optim or root finding by nleqslv converged.

georobObject 35

convergence.code

a diagnostic integer issued by nlminb, optim (component convergence) or nleqslv (component termcd) about convergence.

iter

a named integer vector of length two, indicating either

- the number of function and gradient evaluations when maximizing the (restricted) Gaussian log-likelihood by nlminb or optim, or
- the number of function and Jacobian evaluations when solving the robustified estimating equations by nleqslv.

Tmat

the compressed design matrix for replicated observations at coincident locations (integer vector that contains for each observation the row index of the respective unique location).

cov

a list with covariance matrices (or diagonal variance vectors). Covariance matrices are stored in *compressed form* (see compress) and can be expanded to square matrices by expand. What cov actually contains depends on the flags passed to georob for computing covariances (see control.georob). Possible components are:

- cov.bhat: the covariances of $\widehat{\boldsymbol{B}}$.
- cov. betahat: the covariances of $\widehat{\beta}$.
- cov.delta.bhat: the covariances of $B-\widehat{B}$.
- cov.delta.bhat.betahat: the covariances of $B-\widehat{B}$ and $\widehat{\beta}$.
- cov.ehat: the covariances of $\widehat{\pmb{arepsilon}} = \pmb{Y} \pmb{X} \widehat{\pmb{eta}} \widehat{\pmb{B}}.$
- cov.ehat.p.bhat: the covariances of $\widehat{\varepsilon}+\widehat{B}=Y-X\widehat{eta}$.
- cov.pred.target: a covariance term required for the back-transformation of Kriging predictions of log-transformed data.

expectations

a named numeric vector with the expectations of $\partial \psi_c(x)/\partial x$ (dpsi) and $\psi_c^2(x)$ (psi2) with respect to a standard normal distribution (exp.gauss) and the long-tailed distribution of ε (exp.f0) implied by the choice of the ψ_c -function.

Valphaxi.objects

a list of matrices in *compressed form* with (among others) the following components:

- Valpha: a list with the (generalized) correlation matrices (Valpha) of the nested variogram models structures along with the constants (gcr.constant) added to the respective semivariances matrices.
- Valphaxi: the (generalized) correlation matrix $V_{\alpha,\xi}=\Gamma_{\alpha,\xi}/(\sigma_{\rm n}^2+\sigma^2)$ that includes the spatial nugget effect.
- Valphaxi.inverse: the inverse of $V_{\alpha,\xi}$.
- log.det.Valphaxi: $\log(\det(\boldsymbol{V}_{\alpha,\xi}))$.

zhat.objects

a list of matrices in (partly) compressed form with the following components:

- Aalphaxi: the matrix $(\boldsymbol{X}^T\boldsymbol{V}_{\alpha,\xi}^{-1}\boldsymbol{X})^{-1}\boldsymbol{X}^T\boldsymbol{V}_{\alpha,\xi}^{-1}$.
- Palphaxi: the matrix $I XA_{\alpha, \xi}$.
- Valphaxi.inverse.Palphaxi: the matrix $V_{lpha,\xi}^{-1} P_{lpha,\xi}$.

locations.object

a list with 3 components:

36 georobObject

- locations: a formula indicating the coordinates of the measurement locations
- coordinates: a numeric matrix with the coordinates of the measurement locations.
- lag.vectors: a numeric matrix with the lag vectors between any distinct pairs of measurement locations.

initial.objects

a list with 3 components:

- coefficients: initial estimates of β computed either by 1mrob or rq.
- bhat: initial predictions of **B**.
- variogram. object: the initial values of the parameters of a possibly nested variograms model. This is a list with the same structure as described above for the component variogram. object.

hessian.tfpa

a symmetric matrix with the Hessian (observed Fisher information) at the solution with respect to the transformed variogram and anisotropy parameters if the model was fitted non-robustly with the argument hessian = TRUE (see control.georob). Missing otherwise. This Hessian is used by summary.georob to compute confidence intervals for the estimated parameters.

hessian.ntfpa

a symmetric matrix with the Hessian (observed Fisher information) at the solution with respect to the non-transformed variogram and anisotropy parameters if the model was fitted non-robustly with the argument hessian = TRUE (see control.georob). Missing otherwise.

control

a list with control parameters generated by control.georob.

MD

optionally a matrix of robust distances in the space spanned by X (see argument compute.rd of lmrob.control and control.georob).

model, x, y if requested the model frame, the model matrix and the response, respectively. na.action, offset, contrasts, xlevels, rank, df.residual, call, terms

further components of the fit as described for an object of class 1m.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms;
georob for (robust) fitting of spatial linear models;
profilelogLik for computing profiles of Gaussian likelihoods;
plot.georob for display of RE(ML) variogram estimates;
control.georob for controlling the behaviour of georob;
georobModelBuilding for stepwise building models of class georob;
cv.georob for assessing the goodness of a fit by georob;
georobMethods for further methods for the class georob;
```

predict.georob for computing robust Kriging predictions;

1gnpp for unbiased back-transformation of Kriging prediction of log-transformed data;

georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally

sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.

georobPackage

The georob Package

Description

This is a summary of the features and functionality of **georob**, a package in R for robust geostatistical analyses.

Details

georob is a package for robust analyses of geostatistical data. Such data, say $y_i = y(s_i)$, are recorded at a set of locations, s_i , i = 1, 2, ..., n, in a domain $G \in \mathbb{R}^d$, $d \in (1, 2, 3)$, along with covariate information $x_j(s_i)$, j = 1, 2, ..., p.

Model: We use the following model for the data $y_i = y(s_i)$:

$$Y(s_i) = Z(s_i) + \varepsilon = x(s_i)^{\mathrm{T}} \boldsymbol{\beta} + B(s_i) + \varepsilon_i,$$

where $Z(s_i) = x(s_i)^T \beta + B(s_i)$ is the so-called signal, $x(s_i)^T \beta$ is the external drift, $\{B(s)\}$ is an unobserved stationary or intrinsic spatial Gaussian random field with zero mean, and ε_i is an *i.i.d* error from a possibly long-tailed distribution with scale parameter τ (τ^2 is usually called nugget effect). In vector form the model is written as

$$Y = X\beta + B + \varepsilon$$
.

where \boldsymbol{X} is the model matrix with the rows $\boldsymbol{x}(\boldsymbol{s}_i)^{\mathrm{T}}$.

The (generalized) covariance matrix of the vector of spatial Gaussian random effects \boldsymbol{B} is denoted by

$$\mathrm{E}[\boldsymbol{B}\,\boldsymbol{B}^{\mathrm{T}}] = \boldsymbol{\Gamma}_{\boldsymbol{\theta}} = \sigma_{\mathrm{n}}^{2}\boldsymbol{I} + \sigma^{2}\boldsymbol{V}_{\alpha} = \sigma_{Z}^{2}\,\boldsymbol{V}_{\alpha,\xi} = \sigma_{Z}^{2}\,((1-\xi)\,\boldsymbol{I} + \xi\,\boldsymbol{V}_{\alpha}),$$

where $\sigma_{\rm n}^2$ is the variance of seemingly uncorrelated micro-scale variation in B(s) that cannot be resolved with the chosen sampling design, σ^2 is the variance of the captured auto-correlated variation in B(s), $\sigma_B^2 = \sigma_{\rm n}^2 + \sigma^2$ is the signal variance, and $\xi = \sigma^2/\sigma_B^2$. To estimate both $\sigma_{\rm n}^2$ and τ^2 (and not only their sum), one needs replicated measurements for some of the s_i .

We define $oldsymbol{V}_{lpha}$ to be the matrix with elements

$$(\boldsymbol{V}_{\alpha})_{ij} = \gamma_0 - \gamma(|\boldsymbol{A}(\boldsymbol{s}_i - \boldsymbol{s}_i)|),$$

where the constant γ_0 is chosen large enough so that V_{α} is positive definite, $\gamma(\cdot)$ is a valid stationary or intrinsic variogram, and $A = A(\alpha, f_1, f_2; \omega, \phi, \zeta)$ is a matrix that is used to model geometrically anisotropic auto-correlation. In more detail, A maps an arbitrary point on an ellipsoidal

surface with constant semi-variance in \mathbb{R}^3 , centred on the origin, and having lengths of semi-principal axes, p_1 , p_2 , p_3 , equal to $|p_1| = \alpha$, $|p_2| = f_1 \alpha$ and $|p_3| = f_2 \alpha$, $0 < f_2 \le f_1 \le 1$, respectively, onto the surface of the unit ball centred on the origin.

The orientation of the ellipsoid is defined by the three angles ω , ϕ and ζ :

- ω is the azimuth of p_1 (= angle between north and the projection of p_1 onto the x-y-plane, measured from north to south positive clockwise in degrees),
- ϕ is 90 degrees minus the altitude of p_1 (= angle between the zenith and p_1 , measured from zenith to nadir positive clockwise in degrees), and
- ζ is the angle between p_2 and the direction of the line, say y', defined by the intersection between the x-y-plane and the plane orthogonal to p_1 running through the origin (ζ is measured from y' positive counter-clockwise in degrees).

The transformation matrix is given by

$$m{A} = \left(egin{array}{ccc} 1/lpha & 0 & 0 \ 0 & 1/(f_1 \, lpha) & 0 \ 0 & 0 & 1/(f_2 \, lpha) \end{array}
ight) (m{C}_1, m{C}_2, m{C}_3,)$$

where

$$\boldsymbol{C}_{1}^{\mathrm{T}}=(\sin\omega\sin\phi,-\cos\omega\cos\zeta-\sin\omega\cos\phi\sin\zeta,\cos\omega\sin\zeta-\sin\omega\cos\phi\cos\zeta)$$

$$\boldsymbol{C}_{2}^{\mathrm{T}} = (\cos \omega \sin \phi, \sin \omega \cos \zeta - \cos \omega \cos \phi \sin \zeta, -\sin \omega \sin \zeta - \cos \omega \cos \phi \cos \zeta)$$

$$C_3^{\mathrm{T}} = (\cos\phi, \sin\phi\sin\zeta, \sin\phi\cos\zeta)$$

To model geometrically anisotropic variograms in \mathbb{R}^2 one has to set $\phi = 90$ and $f_2 = 1$, and for $f_1 = f_2 = 1$ one obtains the model for isotropic auto-correlation with range parameter α . Note that for isotropic auto-correlation the software processes data for which d may exceed 3.

Two remarks are in order:

1. Clearly, the (generalized) covariance matrix of the observations Y is given by

$$Cov[\boldsymbol{Y}, \boldsymbol{Y}^{\mathrm{T}}] = \tau^{2} \boldsymbol{I} + \boldsymbol{\Gamma}_{\theta}.$$

2. Depending on the context, the term "variogram parameters" denotes sometimes all parameters of a geometrically anisotropic variogram model, but in places only the parameters of an isotropic variogram model, i.e. $\sigma^2, \ldots, \alpha, \ldots$ and f_1, \ldots, ζ are denoted by the term "anisotropy parameters". In the sequel θ is used to denote all variogram and anisotropy parameters except the nugget effect τ^2 .

Estimation: The unobserved spatial random effects \boldsymbol{B} at the data locations \boldsymbol{s}_i and the model parameters $\boldsymbol{\beta}$, τ^2 and $\boldsymbol{\theta}^T = (\sigma^2, \sigma_n^2, \alpha, \dots, f_1, f_2, \omega, \phi, \zeta)$ are unknown and are estimated in **georob** either by Gaussian or robust restricted maximum likelihood (REML) or Gaussian maximum likelihood (ML). Here ... denote further parameters of the variogram such as the smoothness parameter of the Whittle-Matérn model.

In brief, the robust REML method is based on the insight that for given θ and τ^2 the Kriging predictions (= BLUP) of \boldsymbol{B} and the generalized least squares (GLS = ML) estimates of β can be obtained simultaneously by maximizing

$$-\sum_i \left(\frac{y_i - \boldsymbol{x}(\boldsymbol{s}_i)^{\mathrm{T}}\boldsymbol{\beta} - B(\boldsymbol{s}_i)}{\tau}\right)^2 - \boldsymbol{B}^{\mathrm{T}}\boldsymbol{\Gamma}_{\theta}^{-1}\boldsymbol{B}$$

with respect to \boldsymbol{B} and $\boldsymbol{\beta}$ e.g. Harville (1977).

Hence, the BLUP of B, ML estimates of β , θ and τ^2 are obtained by maximizing

$$-\log(\det(\tau^2 \boldsymbol{I} + \boldsymbol{\Gamma}_{\theta})) - \sum_{i} \left(\frac{y_i - \boldsymbol{x}(\boldsymbol{s}_i)^{\mathrm{T}} \boldsymbol{\beta} - B(\boldsymbol{s}_i)}{\tau}\right)^2 - \boldsymbol{B}^{\mathrm{T}} \boldsymbol{\Gamma}_{\theta}^{-1} \boldsymbol{B}$$

jointly with respect to B, β , θ and τ^2 or by solving the respective estimating equations. The estimating equations can then by robustified by

- replacing the standardized residuals, say ε_i/τ , by a bounded or re-descending ψ -function, $\psi_c(\varepsilon_i/\tau)$, of them (e.g. Marona et al, 2006, chap. 2) and by
- introducing suitable bias correction terms for Fisher consistency at the Gaussian model,

see Kuensch et al. (2011) for details. The robustified estimating equations are solved numerically by a combination of iterated re-weighted least squares (IRWLS) to estimate \boldsymbol{B} and $\boldsymbol{\beta}$ for given $\boldsymbol{\theta}$ and τ^2 and nonlinear root finding by the function nleqslv of the R package nleqslv to get $\boldsymbol{\theta}$ and τ^2 . The robustness of the procedure is controlled by the tuning parameter c of the ψ_c -function. For $c \geq 1000$ the algorithm computes Gaussian (RE)ML estimates and customary plug-in Kriging predictions. Instead of solving the Gaussian (RE)ML estimating equations, our software then maximizes the Gaussian (restricted) log-likelihood using nlminb or optim.

georob uses variogram models implemented in the R package **RandomFields** (see RMmodel). Currently, estimation of the parameters of the following models is implemented:

```
"RMaskey", "RMbessel", "RMcauchy", "RMcircular", "RMcubic", "RMdagum",
```

"RMwhittle".

For most variogram parameters, closed-form expressions of $\partial\gamma/\partial\theta_i$ are used in the computations. However, for the parameter ν of the models "RMbessel", "RMmatern" and "RMwhittle" $\partial\gamma/\partial\nu$ is evaluated numerically by the function numericDeriv, and this results in an increase in computing time when ν is estimated.

Prediction: Robust plug-in external drift point Kriging predictions can be computed for an non-sampled location s_0 from the covariates $x(s_0)$, the estimated parameters $\hat{\beta}$, $\hat{\theta}$ and the predicted random effects \hat{B} by

$$\widehat{Y}(\boldsymbol{s}_0) = \widehat{Z}(\boldsymbol{s}_0) = \boldsymbol{x}(\boldsymbol{s}_0)^{\mathrm{T}} \widehat{\boldsymbol{\beta}} + \boldsymbol{\gamma}_{\widehat{\boldsymbol{\theta}}}^{\mathrm{T}}(\boldsymbol{s}_0) \boldsymbol{\Gamma}_{\widehat{\boldsymbol{\theta}}}^{-1} \widehat{\boldsymbol{B}},$$

where $\Gamma_{\widehat{\theta}}$ is the estimated (generalized) covariance matrix of B and $\gamma_{\widehat{\theta}}(s_0)$ is the vector with the estimated (generalized) covariances between B and $B(s_0)$. Kriging variances can be computed as well, based on approximated covariances of \widehat{B} and $\widehat{\beta}$ (see Künsch et al., 2011, and appendices of Nussbaum et al., 2014, for details).

The package **georob** provides in addition software for computing robust external drift *block* Kriging predictions. The required integrals of the generalized covariance function are computed by functions of the R package **constrainedKriging**.

Functionality: For the time being, the functionality of **georob** is limited to robust geostatistical analyses of *single* response variables. No software is currently available for robust multivariate geostatistical analyses. **georob** offers functions for:

[&]quot;RMdampedcos", "RMdewijsian", "RMexp" (default), "RMfbm", "RMgauss",

[&]quot;RMgencauchy", "RMgenfbm", "RMgengneiting", "RMgneiting", "RMlgd",

[&]quot;RMmatern", "RMpenta", "RMqexp", "RMspheric", "RMstable", "RMwave",

1. Robustly fitting a spatial linear model to data that are possibly contaminated by independent errors from a long-tailed distribution by robust REML (see functions georob — which also fits such models efficiently by Gaussian (RE)ML — profilelogLik and control.georob).

2. Extracting estimated model components (see residuals.georob, rstandard.georob,

ranef.georob).

- 3. Robustly estimating sample variograms and for fitting variogram model functions to them (see sample.variogram and fit.variogram.model).
- 4. Model building by forward and backward selection of covariates for the external drift (see waldtest.georob, step.georob, add1.georob, drop1.georob, extractAIC.georob, logLik.georob, deviance.georob). For a robust fit, the log-likelihood is not defined. The function then computes the (restricted) log-likelihood of an equivalent Gaussian model with heteroscedastic nugget (see deviance.georob for details).
- 5. Assessing the goodness-of-fit and predictive power of the model by *K*-fold cross-validation (see cv.georob and validate.predictions).
- 6. Computing robust external drift point and block Kriging predictions (see predict.georob, control.predict.georob).
- 7. Unbiased back-transformation of both point and block Kriging predictions of log-transformed data to the original scale of the measurements (see lgnpp).

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Nussbaum, M., Papritz, A., Baltensweiler, A. and Walthert, L. (2014) Estimating soil organic carbon stocks of Swiss forest soils by robust external-drift kriging. *Geoscientific Model Development*, 7, 1197–1210. doi: 10.5194/gmd711972014, https://gmd.copernicus.org/articles/7/1197/2014/.

Künsch, H. R., Papritz, A., Schwierz, C. and Stahel, W. A. (in preparation) Robust Geostatistics.

Künsch, H. R., Papritz, A., Schwierz, C. and Stahel, W. A. (2011) Robust estimation of the external drift and the variogram of spatial data. Proceedings of the ISI 58th World Statistics Congress of the International Statistical Institute. doi: 10.3929/ethza009900710

Maronna, R. A., Martin, R. D. and Yohai, V. J. (2006) Robust Statistics Theory and Methods, John Wiley & Sons.

See Also

```
georob for (robust) fitting of spatial linear models;
georobObject for a description of the class georob;
profilelogLik for computing profiles of Gaussian likelihoods;
plot.georob for display of RE(ML) variogram estimates;
control.georob for controlling the behaviour of georob;
georobModelBuilding for stepwise building models of class georob;
```

```
cv.georob for assessing the goodness of a fit by georob;
georobMethods for further methods for the class georob;
predict.georob for computing robust Kriging predictions;
```

lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data;

georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally

sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.

georobS3methods

Common S3 Methods for Class georob

Description

This page documents the methods coef, fixef, fixed.effects, model.frame, model.matrix, nobs, print, ranef, random.effects, resid, residuals, rstandard, summary and vcov for the class georob which extract the respective components or summarize a georob object.

Usage

```
## S3 method for class 'georob'
coef(object, what = c("trend", "variogram"), ...)
## S3 method for class 'georob'
fixef(object, ...)
## S3 method for class 'georob'
fixed.effects(object, ...)
## S3 method for class 'georob'
model.frame(formula, ...)
## S3 method for class 'georob'
model.matrix(object, ...)
## S3 method for class 'georob'
nobs(object, ...)
## S3 method for class 'georob'
print(x, digits = max(3, getOption("digits") - 3), ...)
## S3 method for class 'georob'
ranef(object, standard = FALSE, ...)
## S3 method for class 'georob'
```

```
random.effects(object, standard = FALSE, ...)
## S3 method for class 'georob'
resid(object,
    type = c("working", "response", "deviance", "pearson", "partial"),
    terms = NULL,
    level = 1, \ldots
## S3 method for class 'georob'
residuals(object,
    type = c("working", "response", "deviance", "pearson", "partial"),
    terms = NULL,
    level = 1, \ldots
## S3 method for class 'georob'
rstandard(model, level = 1, ...)
## S3 method for class 'georob'
summary(object, correlation = FALSE, signif = 0.95, ...)
## S3 method for class 'georob'
vcov(object, ...)
```

Arguments

object, model, x

an object of class georob, see georob0bject. formula a model formula or terms object or an object of class georob, see georobObject. correlation logical controlling whether the correlation matrix of the estimated regression coefficients and of the fitted variogram parameters (only for non-robust fits) is computed (default FALSE). digits positive integer indicating the number of decimal digits to print. level an optional integer giving the level for extracting the residuals from object. level = 0 extracts the regression residuals $\widehat{B}(s) + \widehat{\varepsilon}(s)$ and level = 1 (default) only the estimated errors $\widehat{\varepsilon}(s)$. signif confidence level for computing confidence intervals for variogram parameters (default 0.95). standard logical controlling whether the spatial random effects B should be standardized (default FALSE). character keyword indicating the type of residuals to compute, see residuals.lm. type type = "huber" computes 'huberized' residuals $\widehat{\sigma}/\gamma_1\psi(\widehat{\varepsilon}(s)/\widehat{\sigma})$. If type = "terms", which terms (default is all terms). terms what If what = "trend" (default) the function coef extracts the coefficients of the trend model and for what = "variogram" the variogram parameters.

additional arguments passed to methods.

Details

For robust REML fits deviance returns (possibly with a warning) the deviance of the Gaussian REML fit of the equivalent Gaussian spatial linear model with heteroscedastic nugget.

The methods model.frame, model.matrix and nobs extract the model frame, model matrix and the number of observations, see help pages of respective generic functions.

The methods residuals (and resid) extract either the estimated independent errors $\widehat{\varepsilon}(s)$ or the sum of the latter quantities and the spatial random effects $\widehat{B}(s)$. rstandard does the same but standardizes the residuals to unit variance. ranef (random.effects) extracts the spatial random effects with the option to standardize them as well, and fixef (fixed.effects) extracts the fitted fixed-effects regression coefficients, which may of course also be obtained by coef.

For Gaussian REML the method summary computes confidence intervals of the estimated variogram and anisotropy parameters from the Hessian matrix of the (restricted) log-likelihood (= observed Fisher information), based on the asymptotic normal distribution of (RE)ML estimates. Note that the Hessian matrix with respect to the *transformed* variogram and anisotropy parameters is used for this. Hence the inverse Hessian matrix is the covariance matrix of the transformed parameters, confidence intervals are first computed for the transformed parameters and the limits of these intervals are transformed back to the original scale of the parameters. Optionally, summary reports the correlation matrix of the *transformed* parameters, also computed from the Hessian matrix.

Note that the methods coef and summary generate objects of class coef. georob and summary. georob, respectively, for which only print methods are available.

Besides, the default methods of the generic functions confint, df.residual, fitted, formula, termplot and update can be used for objects of class georob.

Value

The methods fixef, fixed.effects and coef return the numeric vector of estimated fixed-effects regression coefficients or variogram and anisotropy parameters (coef only), and vcov returns the covariance matrix of the estimated regression coefficients.

The methods resid, residuals and rstandard return numeric vectors of (standardized) residuals, and ranef and random.effects the numeric vector of (standardized) spatial random effects, see *Details*.

The methods model.frame and model.matrix return a model frame and the fixed-effects model matrix, respectively, and nobs returns the number of observations used to fit a spatial linear model.

The method summary generates a list with components extracted directly from object (call, residuals, bhat, rweights, converged, convergence.code, iter, loglik, variogram.object, gradient, tuning.psi, df.residual, control, terms) and complements the list by the following components:

scale the square root of the estimated nugget effect τ^2 .

coefficients a 4-column matrix with estimated regression coefficients, their standard errors *t*-statistics and corresponding (two-sided) *p*-values.

correlation an optional lower-triagonal matrix with the Pearson correlation coefficients of the estimated regression coefficients.

param.aniso either a vector (robust REML) or a 3-column matrix (Gaussian REML) with estimated variogram and anisotropy parameters, complemented for Gaussian REML with confidence limits, see *Details*.

cor.tf.param an optional lower-triagonal matrix with the Pearson correlation coefficients of estimated transformed variogram and anisotropy parameters, see *Details*.

se.residuals a vector with the standard errors of the estimated ε .

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; georobObject for a description of the class georob; profilelogLik for computing profiles of Gaussian likelihoods; plot.georob for display of RE(ML) variogram estimates; control.georob for controlling the behaviour of georob; georobModelBuilding for stepwise building models of class georob; cv.georob for assessing the goodness of a fit by georob; predict.georob for computing robust Kriging predictions; lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data; georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

Examples

```
## Not run:
data(meuse)

## Gaussian REML fit
r.logzn.reml <- georob(log(zinc) ~ sqrt(dist), data = meuse, locations = ~ x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1000)

summary(r.logzn.reml, correlation = TRUE)

## robust REML fit
r.logzn.rob <- update(r.logzn.reml, tuning.psi = 1)

summary(r.logzn.rob, correlation = TRUE)

## residual diagnostics
old.par <- par(mfrow = c(2,3))

plot(fitted(r.logzn.reml), rstandard(r.logzn.reml))</pre>
```

```
abline(h = 0, lty = "dotted")
qqnorm(rstandard(r.logzn.reml))
abline(0, 1)
qqnorm(ranef(r.logzn.reml, standard = TRUE))
abline(0, 1)
plot(fitted(r.logzn.rob), rstandard(r.logzn.rob))
abline(h = 0, lty = "dotted")
qqnorm(rstandard(r.logzn.rob))
abline(0, 1)
qqnorm(ranef(r.logzn.rob, standard = TRUE))
abline(0, 1)
par(old.par)
## End(Not run)
```

georobSimulation

Simulating Realizations of Gaussian Processes from Object of Class georob

Description

This page documents the function condsim that simulates (un)conditional realizations of Gaussian processes from the parameters of a spatial linear model estimated by the function georob.

Usage

```
condsim(object, newdata, nsim, seed,
  type = c("response", "signal"), locations, trend.coef = NULL,
  variogram.model = NULL, param = NULL, aniso = NULL, variogram.object = NULL,
  control = control.condsim(), verbose = 0)

control.condsim(use.grid = FALSE, grid.refinement = 2.,
  condsim = TRUE, include.data.sites = FALSE, means = FALSE,
  trend.covariates = FALSE, covariances = FALSE,
  ncores = detectCores(), pcmp = control.pcmp())
```

Arguments

object	an object of class georob (mandatory argument), see georobObject.	
newdata	a mandatory data frame, SpatialPointsDataFrame, SpatialPixelsDataFrame, SpatialGridDataFrame, SpatialPoints, SpatialPixels or SpatialGrid object, with the coordinates of points for which simulations are computed and in which to look for variables required for computing fitted values or Kriging predictions, see predict.georob.	
nsim	number of (condititional) realizations to compute (mandatory argument).	
seed	integer seed to initialize random number generation, see set.seed (mandatory argument).	

character keyword defining what target quantity should be simulated. Possible type values are

- "signal": the "signal" $Z(s) = x(s)^{\mathrm{T}} \beta + B(s)$ of the process,
- "response": the observations $Y(s) = Z(s) + \varepsilon(s)$, (default),

see georobIntro for details on the model specification.

locations an optional one-sided formula specifying what variables of newdata are the

coordinates of the points for which simulated values are computed (default:

object[["locations.objects"]][["locations"]]).

trend.coef an optional numeric vector with the coefficients of the trend model to be used for

computing the (conditional) mean function of the random process see *Details*.

variogram.model

an optional character keyword defining the variogram model to be used for the

simulations, see georob and *Details*.

an optional named numeric vector with values of the variogram parameters used param

for the simulations, see georob and Details.

aniso an optional named numeric vector with values of anisotropy parameters of a

variogram used for the simulations, see georob and Details.

variogram.object

an optional list that defines a possibly nested variogram model used for the sim-

ulations, see georob and *Details*.

control a list with the components use.grid, grid.refinement, condsim,

> include.data.sites, means, trend.covariates, covariances, ncores, and pcmp or a function such as control.condsim that generates such a list, see

arguments of control.condsim for details.

verbose positive integer controlling logging of diagnostic messages to the console.

verbose = 0 (default) suppresses such messages.

logical scalar (default FALSE) to control whether (conditional) realizations are use.grid

computed for a rectangular grid instead of the coordinates of points contained in

newdata, see Details.

grid.refinement

numeric scalar that defines a factor by which the minimum differences of the coordinates between any pair of points in newdata are divided to setup the sim-

ulation grid, should be > 1 (default 2), see *Details*.

logical scalar (default TRUE) to control whether conditional (TRUE) or uncondicondsim

tional simulations (FALSE) are computed.

include.data.sites

logical scalar, to control whether (conditionally) simulated values are returned also for the points of the original data set used to estimate the model parameters.

logical scalar, to control whether the (un)conditional means are included in the

output.

trend.covariates

logical scalar, to control whether the covariates required for the trend model are included in the output.

means

covariances logical scalar, to control whether the covariances between the points of the origi-

nal data set used to estimate the model parameters (attr gcvmat.d.d, compressed matrix) and the covariances between the simulation and the original data points (attr gcvmat.s.d, matrix) are returned as attributes of the output. Note that

these covariances are only returned if use.grid == TRUE & condsim == TRUE.

ncores positive integer controlling how many cores are used for parallelized computa-

tions, defaults to all cores.

pcmp a list of arguments, passed e.g. to pmm or a function such as control.pcmp that

generates such a list (see control.pcmp for allowed arguments).

Details

condsim (conditionally) simulates from a Gaussian process that has a linear mean function with parameters β and an auto-correlation structure characterized by a parametric variogram model and variogram parameters τ^2 and θ (see georobIntro for the employed parametrization of the spatial linear model). The parameters of the mean and auto-correlation function are either taken from the the spatial linear model estimated by georob and passed by the argument object to condsim or from the optional arguments trend.coef (β) and variogram.model, param, aniso or variogram.object (τ^2, θ) . Note that in the former case the uncertainty in the estimated mean and auto-correlation parameters is not taken into account.

Simulated values are computed for the points in newdata by the function RFsimulate of the package **RandomFields**. Both unconditional and conditional simulations can be computed. In the latter cases, the simulated values are always conditioned to the response data used to fit the spatial linear model by georob and contained in object.

Unconditional simulation:

Unconditional realizations are either computed for the exact locations of the points in newdata (use.grid == FALSE), irrespective of the fact whether these are arranged on a regular grid, or for the (approximate) locations of the points in newdata matched to a rectangular simulation grid (use.grid == TRUE). The latter approach may be substantially faster for large problems because the simulation algorithm implemented in RFsimulate for grids is faster than for arbitrary geometries of the simulation points.

For use.grid == TRUE, a rectangular grid is constructed from the coordinates of the points in newdata and object. The spacing of the grid is equal to the minimum distance between any pair of points in newdata, divided by grid.refinement. The data related to the points in newdata (covariates for the trend model) and of the data in object (response values, covariates) are then assigned to the nodes of the grid that are closest to the respective points. If the same grid node is assigned to several points in newdata (or in object) then the data of the respective points are averaged. If the same node is assigned to a point in object and newdata then the point in object is kept and the concerned point in newdata is omitted.

Conditional simulation:

Simulations are conditioned to data either by exploiting the respective built-in functionality of RFsimulate (use.grid == FALSE) or by the Kriging method (use.grid == TRUE, see Chilès and Delfiner, 1999, sec. 7.3). The latter approach may again be faster for large problems because it exploits the larger speed of unconditional simulations for rectangular grids.

Parallelized computations:

condsim uses the packages **parallel**, **snow** and **snowfall** for parallelized computation of simulations. If there are m realizations to simulate, the task is split into ceiling(m/ncores) sub-tasks that are then distributed to ncores CPUs. Evidently, ncores = 1 suppresses parallel execution. By default, the function uses all available CPUs as returned by detectCores.

Value

The output generated by condsim is an object of a "similar" class as newdata (data frame, SpatialPointsDataFrame, SpatialPixelsDataFrame, SpatialGridDataFrame, SpatialPolygonsDataFrame).

The data frame or the data slot of the Spatial...DataFrame objects have the following components:

- the coordinates of the prediction points (only present if newdata is a data frame).
- expct: optionally the (un)conditional means.
- optionally the covariates required for the trend model.
- sim. 1, sim. 2, ...: the (un)conditionally simulated realizations.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Chilès, J.-P. and Delfiner, P. (1999) *Geostatistics: Modeling Spatial Uncertainty*, John Wiley & Sons, New York.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; georobObject for a description of the class georob; profilelogLik for computing profiles of Gaussian likelihoods; plot.georob for display of RE(ML) variogram estimates; control.georob for controlling the behaviour of georob; georobModelBuilding for stepwise building models of class georob; cv.georob for assessing the goodness of a fit by georob; georobMethods for further methods for the class georob; predict.georob for computing robust Kriging predictions; lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data; sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

lgnpp 49

Examples

```
## Not run:
data(meuse)
data(meuse.grid)
## convert to SpatialGridDataFrame
meuse.grid.sgdf <- meuse.grid</pre>
coordinates(meuse.grid.sgdf) <- \sim x + y
gridded(meuse.grid.sgdf) <- TRUE</pre>
fullgrid(meuse.grid.sgdf) <- TRUE</pre>
## Gaussian REML fit
r.logzn.reml \leftarrow georob(log(zinc) \sim sqrt(dist), data = meuse, locations = \sim x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1000)
## Conditional simulations
r.sim <- condsim(r.logzn.reml, newdata = meuse.grid.sgdf, nsim = 100, seed = 1,</pre>
    control = control.condsim(ncores = 1))
## using multiple cores
## r.sim <- condsim(r.logzn.reml, newdata = meuse.grid.sgdf, nsim = 100, seed = 1)
str(r.sim, max=2)
## Display
spplot(r.sim, zcol = "sim.1", at = seg(3.5, 8.5, by = 0.5))
spplot(r.sim, zcol = "sim.2", at = seq(3.5, 8.5, by = 0.5))
library(lattice)
levelplot(sim.1 \sim x + y, as.data.frame(r.sim), aspect = "iso", at = seq(3.5, 8.5, by = 0.5),
  panel = function(x, y, z, subscripts, data.points, ...){
    panel.levelplot( x, y, z, subscripts, ...)
    panel.xyplot(data.points$x, data.points$y, col = 1)
  }, data.points = meuse[, c("x", "y")]
levelplot(sim.2 \sim x + y, as.data.frame(r.sim), aspect = "iso", at = seq(3.5, 8.5, by = 0.5),
  panel = function(x, y, z, subscripts, data.points, ...){
    panel.levelplot( x, y, z, subscripts, ...)
    panel.xyplot(data.points$x, data.points$y, col = 1)
  }, data.points = meuse[, c("x", "y")]
)
## End(Not run)
```

1gnpp

Description

The function 1gnpp back-transforms point or block Kriging predictions of a log-transformed response variable computed by predict.georob. Alternatively, the function averages log-normal point Kriging predictions for a block and approximates the mean squared prediction error of the block mean.

Usage

```
lgnpp(object, newdata, locations, is.block = FALSE, all.pred = NULL,
    extended.output = FALSE)
```

Arguments

object	an object with Kriging predictions of a log-transformed response variable as obtained by predict(georob-object,).	
newdata	an optional object as passed as argument newdata to predict. georob, see <i>Details</i> .	
locations	an optional one-sided formula specifying what variables of newdata are the coordinates of the prediction points, see predict.georob .	
is.block	an optional logical (default FALSE) specifying whether point predictions contained in object are considered to belong to a single block and should be averaged after back-transformation. Ignored if object contains block Kriging predictions, see <i>Details</i> .	
all.pred	an optional positive integer or an object as obtained by lgnpp(predict(georobobject,)), see <i>Details</i> .	

logical controlling whether the covariance matrix of the errors of the back-transformed point predictions is added as an attribute to the result, see *Details*.

Details

extended.output

The function 1gnpp performs three tasks:

1. Back-transformation of point Kriging predictions of a log-transformed response:

The usual, marginally unbiased back-transformation for log-normal point Kriging is used:

$$\begin{split} \widehat{U}(\boldsymbol{s}) &= \exp(\widehat{Z}(\boldsymbol{s}) + 1/2(\operatorname{Var}_{\widehat{\theta}}[Z(\boldsymbol{s})] - \operatorname{Var}_{\widehat{\theta}}[\widehat{Z}(\boldsymbol{s})])), \\ & \operatorname{Cov}_{\widehat{\theta}}[U(\boldsymbol{s}_i) - \widehat{U}(\boldsymbol{s}_i), U(\boldsymbol{s}_j) - \widehat{U}(\boldsymbol{s}_j)] = \mu_{\widehat{\theta}}(\boldsymbol{s}_i)\mu_{\widehat{\theta}}(\boldsymbol{s}_j) \\ & \times \{ \exp(\operatorname{Cov}_{\widehat{\theta}}[Z(\boldsymbol{s}_i), Z(\boldsymbol{s}_j)]) - 2\exp(\operatorname{Cov}_{\widehat{\theta}}[\widehat{Z}(\boldsymbol{s}_i), Z(\boldsymbol{s}_j)]) + \exp(\operatorname{Cov}_{\widehat{\theta}}[\widehat{Z}(\boldsymbol{s}_i), \widehat{Z}(\boldsymbol{s}_j)]) \}, \end{split}$$

where \widehat{Z} and \widehat{U} denote the log- and back-transformed predictions of the signal, and

$$\mu_{\hat{\theta}}(s) \approx \exp(x(s)^{\mathrm{T}} \hat{\boldsymbol{\beta}} + 1/2 \mathrm{Var}_{\hat{\theta}}[Z(s)]).$$

lgnpp 51

The expressions for the required covariance terms can be found in the Appendices of Nussbaum et al. (2014). Instead of the signal Z(s), predictions of the log-transformed response Y(s) or the estimated trend $x(s)^{\mathrm{T}}\widehat{\beta}$ of the log-transformed data can be back-transformed (see georobIntro). The above transformations are used if object contains point Kriging predictions (see predict.georob, Value) and if is.block = FALSE and all.pred is missing.

2. Back-transformation of block Kriging predictions of a log-transformed response:

Block Kriging predictions of a log-transformed response variable are back-transformed by the approximately unbiased transformation proposed by Cressie (2006, Appendix C)

$$\widehat{U}(A) = \exp(\widehat{Z}(A) + 1/2\{\operatorname{Var}_{\widehat{\boldsymbol{\theta}}}[Z(\boldsymbol{s})] + \widehat{\boldsymbol{\beta}}^{\mathrm{T}}\boldsymbol{M}(A)\widehat{\boldsymbol{\beta}} - \operatorname{Var}_{\widehat{\boldsymbol{\theta}}}[\widehat{Z}(A)]\}),$$

$$\mathbf{E}_{\hat{\theta}}[\{U(A)-\widehat{U}(A))^2] = \mu_{\hat{\theta}}(A)^2\{\exp(\mathrm{Var}_{\hat{\theta}}[Z(A)]) - 2\exp(\mathrm{Cov}_{\hat{\theta}}[\widehat{Z}(A),Z(A)]) + \exp(\mathrm{Var}_{\hat{\theta}}[\widehat{Z}(A)])\}$$

where $\widehat{Z}(A)$ and $\widehat{U}(A)$ are the log- and back-transformed predictions of the block mean U(A), respectively, M(A) is the spatial covariance matrix of the covariates

$$oldsymbol{M}(A) = 1/|A| \int_A (oldsymbol{x}(oldsymbol{s}) - oldsymbol{x}(A)) (oldsymbol{x}(oldsymbol{s}) - oldsymbol{x}(A))^{ ext{T}} doldsymbol{s}$$

within the block A where

$$oldsymbol{x}(A) = 1/|A| \int_A oldsymbol{x}(oldsymbol{s}) \, doldsymbol{s}$$

and

$$\mu_{\hat{\theta}}(A) \approx \exp(\boldsymbol{x}(A)^{\mathrm{T}}\widehat{\boldsymbol{\beta}} + 1/2\mathrm{Var}_{\hat{\theta}}[Z(A)]).$$

This back-transformation is based on the assumption that both the point data U(s) and the block means U(A) follow log-normal laws, which strictly cannot hold. But for small blocks the assumption works well as the bias and the loss of efficiency caused by this assumption are small (Cressie, 2006; Hofer et al., 2013).

The above formulae are used by lgnpp if object contains block Kriging predictions in the form of a SpatialPolygonsDataFrame. To approximate M(A), one needs the covariates on a fine grid for the whole study domain in which the blocks lie. The covariates are passed lgnpp as argument newdata, where newdata can be any spatial data frame accepted by predict.georob. For evaluating M(A) the geometry of the blocks is taken from the polygons slot of the SpatialPolygonsDataFrame passed as object to lgnpp.

3. Back-transformation and averaging of point Kriging predictions of a log-transformed response:

lgnpp allows as a further option to back-transform and *average* point Kriging predictions passed as object to the function. One then assumes that the predictions in object refer to points that lie in *a single* block. Hence, one uses the approximation

$$\widehat{U}(A) \approx \frac{1}{K} \sum_{s_i \in A} \widehat{U}(s_i)$$

to predict the block mean U(A), where K is the number of points in A. The mean squared prediction error can be approximated by

$$E_{\hat{\theta}}[\{U(A) - \widehat{U}(A)\}^2] \approx \frac{1}{K^2} \sum_{s_i \in A} \sum_{s_j \in A} \operatorname{Cov}_{\hat{\theta}}[U(s_i) - \widehat{U}(s_i), U(s_j) - \widehat{U}(s_j)].$$

In most instances, the evaluation of the above double sum is not feasible because a large number of points is used to discretize the block A. Ignpp then uses the following approximations to compute the mean squared error (see also Appendix E of Nussbaum et al., 2014):

- Point prediction results are passed as object to 1gnpp only for a random sample of points in
 A (of size k), for which the evaluation of the above double sum is feasible.
- The prediction results for the *complete set of points* within the block are passed as argument all.pred to lgnpp. These results are used to compute $\widehat{U}(A)$.
- The mean squared error is then approximated by

$$\mathrm{E}_{\hat{\theta}}[\{U(A) - \widehat{U}(A)\}^2] \approx \frac{1}{K^2} \sum_{s_i \in A} \mathrm{E}_{\hat{\theta}}[\{U(s_i) - \widehat{U}(s_i)\}^2]$$

$$+ \frac{K-1}{Kk(k-1)} \sum_{s_i \in \text{sample } s_j \in \text{sample}, s_j \neq s_i} \text{Cov}_{\hat{\theta}}[U(\boldsymbol{s}_i) - \widehat{U}(\boldsymbol{s}_i), U(\boldsymbol{s}_j) - \widehat{U}(\boldsymbol{s}_j)].$$

The first term of the RHS (and $\widehat{U}(A)$) can be computed from the point Kriging results contained in all.pred, and the double sum is evaluated from the full covariance matrices of the predictions and the respective targets, passed to lgnpp as object (one has to use the arguments control=control.predict.georob(full.covmat=TRUE) for predict.georob when computing the point Kriging predictions stored in object).

• If the prediction results are not available for the complete set of points in A then all.pred may be equal to K. The block mean is then approximated by

$$\widehat{U}(A) \approx \frac{1}{k} \sum_{s_i \in \text{sample}} \widehat{U}(s_i)$$

and the first term of the RHS of the expression for the mean squared error by

$$\frac{1}{kK} \sum_{s_i \in \text{sample}} \mathrm{E}_{\hat{\theta}}[\{U(s_i) - \widehat{U}(s_i)\}^2].$$

• By drawing samples repeatedly and passing the related Kriging results as object to 1gnpp, one can reduce the error of the approximation of the mean squared error.

Value

If is.block is FALSE and all.pred is equal to NULL an updated object of the same class as object (see section *Value* of predict.georob). The data frame with the point or block Kriging predictions is complemented by lgnpp with the following new components:

• lgn.pred: the back-transformed Kriging predictions of a log-transformed response.

Ignpp 53

- 1gn. se: the standard errors of the back-transformed predictions.
- lgn.lower, lgn.upper: the bounds of the back-transformed prediction intervals.

If is.block is TRUE or all.pred not equal to NULL a named numeric vector with two elements:

- mean: the back-transformed block Kriging estimate, see *Details*.
- se: the (approximated) block Kriging standard error, see *Details*.

If extended.output is TRUE then the vector is supplemented with the attribute mse.lgn.pred that contains the full covariance matrix of the back-transformed point prediction errors.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Cressie, N. (2006) Block Kriging for Lognormal Spatial Processes. *Mathematical Geology*, **38**, 413–443.

Hofer, C., Borer, F., Bono, R., Kayser, A. and Papritz, A. 2013. Predicting topsoil heavy metal content of parcels of land: An empirical validation of customary and constrained lognormal block Kriging and conditional simulations. *Geoderma*, **193–194**, 200–212.

Nussbaum, M., Papritz, A., Baltensweiler, A. and Walthert, L. (2014) Estimating soil organic carbon stocks of Swiss forest soils by robust external-drift kriging. *Geoscientific Model Development*, 7, 1197–1210. doi: 10.5194/gmd711972014, https://gmd.copernicus.org/articles/7/1197/2014/.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; predict.georob for computing robust Kriging predictions.
```

Examples

```
## Not run:
data(meuse)

data(meuse.grid)
coordinates(meuse.grid) <- ~x+y
meuse.grid.pixdf <- meuse.grid
gridded(meuse.grid.pixdf) <- TRUE

library(constrainedKriging)
data(meuse.blocks)

r.logzn.rob <- georob(log(zinc) ~ sqrt(dist), data = meuse, locations = ~ x + y,
    variogram.model = "RMexp", param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1., control = control.georob(cov.bhat = TRUE, full.cov.bhat = TRUE))</pre>
```

54 param.names

```
## point predictions of log(Zn)
r.pred.points <- predict(r.logzn.rob, newdata = meuse.grid.pixdf,</pre>
    control = control.predict.georob(extended.output = TRUE, full.covmat = TRUE))
str(r.pred.points$pred@data)
## back-transformation of point predictions
r.backtf.pred.points <- lgnpp(r.pred.points)</pre>
str(r.backtf.pred.points$pred@data)
spplot(r.backtf.pred.points[["pred"]], zcol = "lgn.pred", main = "Zn content")
## predicting mean Zn content for whole area
r.block <- lgnpp(r.pred.points, is.block = TRUE, all.pred = r.backtf.pred.points[["pred"]])</pre>
r.block
## block predictions of log(Zn)
r.pred.block <- predict(r.logzn.rob, newdata = meuse.blocks,</pre>
    control = control.predict.georob(extended.output = TRUE,
        pwidth = 75, pheight = 75)
r.backtf.pred.block <- lgnpp(r.pred.block, newdata = meuse.grid)</pre>
spplot(r.backtf.pred.block, zcol = "lgn.pred", main = "block means Zn content")
## End(Not run)
```

param.names

Names and Permissible Ranges of Variogram Parameters

Description

Helper functions to query names and permissible ranges of variogram parameters.

Usage

```
param.names(model)
param.bounds(model, d)
```

Arguments

model character keyword denoting a valid variogram, see georob and georobIntro.

d number of dimensions of the survey domain.

Value

Either a character vector with the names of the additional variogram parameters such as the smoothness parameter of the Whittle-Matérn model (param.names) or a named list with the lower and upper bounds of permissible parameter ranges.

plot.georob 55

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models.

Examples

```
param.names("RMgengneiting")
param.bounds("RMgengneiting", d = 2)
```

plot.georob

Plot Methods for Class georob

Description

The plot and lines methods for class georob plot the variogram model, estimated by (robust) restricted maximum likelihood. plot. georob computes and plots in addition the sample variogram of the (robust) regression residuals and can be used to generate residual diagnostics plots (Tukey-Anscombe plot, normal QQ plots of residuals and random effects).

Usage

```
## S3 method for class 'georob'
plot(x, what = c( "variogram", "covariance", "correlation",
    "ta", "sl", "qq.res", "qq.ranef" ), add = FALSE, lag.dist.def,
    xy.angle.def = c(0, 180), xz.angle.def = c(0, 180), max.lag = Inf,
    estimator = c("mad", "qn", "ch", "matheron"), mean.angle = TRUE,
    level = what != "ta", smooth = what == "ta" || what == "sl",
    id.n = 3, labels.id = names(residuals(x)), cex.id = 0.75,
    label.pos = c(4,2), col, pch, xlab, ylab, main, lty = "solid", ...)

## S3 method for class 'georob'
lines(x, what = c("variogram", "covariance", "correlation"),
    from = 1.e-6, to, n = 501, xy.angle = 90, xz.angle = 90,
    col = 1:length(xy.angle), pch = 1:length(xz.angle), lty = "solid", ...)
```

Arguments

what

x an ol

an object of class georob, see georob0bject.

character keyword for the quantity that should be displayed. Possible values are:

- "variogram": the variogram
- "covariance": the covariance function
- "correlation": the correlation function

56 plot.georob

 "scale-location": square root of absolute regression residuals plotted against fitted values (Scale-Location plot)

- "ta": regression residuals plotted against fitted values (Tukey-Anscombe plot)
- "qq.res": normal Q-Q plot of standardized errors $\hat{\varepsilon}$
- "qq.ranef": normal Q-Q plot of standardized random effects \hat{B}

add

logical controlling whether a new plot should be generated (FALSE, default) or whether the information should be added to the current plot (TRUE).

lag.dist.def

an optional numeric scalar defining a constant bin width for grouping the lag distances or an optional numeric vector with the upper bounds of a set of contiguous bins for computing the sample variogram of the regression residuals, see sample.variogram. If missing then the sample variogram is not computed.

xy.angle.def

an numeric vector defining angular classes in the horizontal plane for computing directional variograms. xy.angle.def must contain an ascending sequence of azimuth angles in degrees from north (positive clockwise to south), see sample.variogram. Omnidirectional variograms are computed with the default c(0,180).

xz.angle.def

an numeric vector defining angular classes in the x-z-plane for computing directional variograms. xz.angle.def must contain an ascending sequence of angles in degrees from zenith (positive clockwise to nadir), see sample.variogram. Omnidirectional variograms are computed with the default c(0,180).

max.lag

positive numeric defining the largest lag distance for which semi-variances should be computed (default no restriction).

estimator

character keyword defining the estimator for computing the sample variogram. Possible values are:

- "qn": Genton's robust Qn-estimator (default, Genton, 1998),
- "mad": Dowd's robust MAD-estimator (Dowd, 1984),
- "matheron": non-robust method-of-moments estimator,
- "ch": robust Cressie-Hawkins estimator (Cressie and Hawkins, 1980).

mean.angle

logical controlling whether the mean lag vector (per combination of lag distance and angular class) is computed from the mean angles of all the lag vectors falling into a given class (TRUE, default) or from the mid-angles of the respective angular classes (FALSE).

level

an integer giving the level for extracting the residuals from object for what = "ta" or what = "qq.res". level = 0 (default for what == "ta") extracts the regression residuals $\widehat{B}(s)+\widehat{\varepsilon}(s)$ and level = 1 (default for what == "qq.res") only the estimated errors $\widehat{\varepsilon}(s)$.

smooth

logical controlling whether a loess.smooth is added to the Tukey-Anscombe plot (default TRUE.

id.n

number of points to be labelled in each plot, starting with the most extreme (see plot.lmrob).

labels.id

vector of labels, from which the labels for extreme points will be chosen (see plot.lmrob). NULL uses observation numbers.

plot.georob 57

cex.id	magnification of point labels (see plot.lmrob).
label.pos	positioning of labels, for the left half and right half of the graph respectively (see ${\tt plot.lmrob}$).
from	numeric, minimal lag distance for plotting variogram models.
to	numeric, maximum lag distance for plotting variogram models (default: largest lag distance of current plot).
n	positive integer specifying the number of equally spaced lag distances for which semi-variances are evaluated in plotting variogram models (default 501).
xy.angle	numeric (vector) with azimuth angles (in degrees, clockwise positive from north) in x - y -plane for which semi-variances should be plotted.
xz.angle	numeric (vector) with angles in x - z -plane (in degrees, clockwise positive from zenith to south) for which semi-variances should be plotted.
col	optional color of points and curves to distinguish items relating to different azimuth angles in $x\hbox{-} y\hbox{-} {\rm plane}.$
pch	optional symbol for points and curves to distinguish items relating to different azimuth angles in $x\hbox{-} z\hbox{-plane}.$
lty	line type for plotting variogram models.
xlab, ylab, main	
	test annotation, see plot.
•••	additional arguments passed to $\verb"plot.sample.variogram"$, $\verb"loess.smooth"$ and graphical methods.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; georobObject for a description of the class georob; profilelogLik for computing profiles of Gaussian likelihoods; control.georob for controlling the behaviour of georob; georobModelBuilding for stepwise building models of class georob; cv.georob for assessing the goodness of a fit by georob; georobMethods for further methods for the class georob; predict.georob for computing robust Kriging predictions; lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data; georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

58 pmm

Examples

```
## Not run:
################
## meuse data ##
##################
data(meuse)
## Gaussian REML fit
r.logzn.reml \leftarrow georob(log(zinc) \sim sqrt(dist), data = meuse, locations = \sim x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1000)
summary(r.logzn.reml, correlation = TRUE)
## robust REML fit
r.logzn.rob <- update(r.logzn.reml, tuning.psi = 1)</pre>
summary(r.logzn.rob, correlation = TRUE)
plot(r.logzn.reml, lag.dist.def = seq(0, 2000, by = 100))
lines(r.logzn.rob, col = "red")
## End(Not run)
```

pmm

Parallelized Matrix Multiplication

Description

This page documents the function pmm for parallelized matrix multiplication and the function control.pcmp, which controls the behaviour of pmm and other functions that execute tasks in parallel.

Usage

```
pmm(A, B, control = control.pcmp())
control.pcmp(pmm.ncores = 1, gcr.ncores = 1, max.ncores = detectCores(),
    f = 1, sfstop = FALSE, allow.recursive = TRUE,
    fork = !identical(.Platform[["OS.type"]], "windows"), ...)
```

Arguments

A, B	matrices to be multiplied.	
control	a list of with the arguments $pmm.ncores$, $gcr.ncores$, $max.ncores$, f, $sfstop$ and allow.recursive or a function such as $control.pcmp$ that generates such a list.	
pmm.ncores	number (integer, default 1) of cores used for parallelized matrix multiplication.	

pmm 59

gcr.ncores	number (integer, default 1) of cores used for parallelized computation of semi-variance matrix.
max.ncores	maximum number of cores (integer, default all cores of a machine) used for parallelized computations.
f	number (integer, default 2) of tasks assigned to each core in parallelized operations.
sfstop	logical controlling whether the SNOW socket cluster is stopped after each parallelized matrix multiplication on windows OS (default FALSE).
allow.recursive	
	logical controlling whether nested parallelized computation should be allowed (default TRUE).
fork	logical controlling whether forking should be used for parallel computations (default TRUE on unix and FALSE on windows operating systems). Note that settting fork == TRUE on windows suppresses parallel computations.
	further arguments, currently not used.

Details

Parallelized matrix multiplication shortens computing time for large data sets (n > 1000). However, spawning child processes requires itself resources and increasing the number of cores for parallel matrix multiplication does not always result in reduced computing time. A sensible default for the number of cores is likely pmm.ncores=2.

Note, however, that very substantial reductions in computing time results when one uses the **Open-BLAS** library instead of the reference BLAS library that ships with R, see https://www.openblas.net/ and R FAQ for your OS. With OpenBLAS no gains are obtained by using more than one core for matrix multiplication, and one should therefore use the default argument pmm.ncores = 1 for control.pcmp().

max.ncores controls how many child processes are spawned in total. This can be used to prevent that child processes spawn themselves children which may result in a considerable number of child processes.

Value

```
pmm: the matrix product A %*% B,
control.pcmp: a list with components pmm.ncores, gcr.ncores, max.ncores, f, sfstop,
    allow.recursive.
```

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models.
```

Examples

```
## Not run:
A <- as.matrix(dist(rnorm(2000)))
B <- as.matrix(dist(rnorm(2000)))
system.time(C <- pmm(A, B, control = control.pcmp(pmm.ncores = 1)))
## using 4 cores
## system.time(C <- pmm(A, B, control = control.pcmp(pmm.ncores = 4)))
## End(Not run)</pre>
```

predict.georob

Predict Method for Robustly Fitted Spatial Linear Models

Description

Robust and customary external drift Kriging prediction based on a spatial linear models fitted by georob. The predict method for the class georob computes fitted values, point and block Kriging predictions as well as model terms for display by termplot.

Usage

```
## S3 method for class 'georob'
predict(object, newdata, type = c("signal", "response", "trend", "terms"),
    terms = NULL, se.fit = TRUE, signif = 0.95, locations,
    variogram.model = NULL, param = NULL, aniso = NULL, variogram.object = NULL,
    control = control.predict.georob(), verbose = 0, ...)

control.predict.georob(full.covmat = FALSE, extended.output = FALSE,
    mmax = 10000, ncores = pcmp[["max.ncores"]], pwidth = NULL, pheight = NULL,
    napp = 1, pcmp = control.pcmp())
```

Arguments

object

an object of class "georob" (mandatory argument), see georob0bject.

newdata

an optional data frame, SpatialPointsDataFrame, SpatialPixelsDataFrame, SpatialGridDataFrame, SpatialPolygonsDataFrame or an (optional) object of class SpatialPoints, SpatialPixels or SpatialGrid, in which to look for variables with which to compute fitted values or Kriging predictions, see Details.

If newdata is a SpatialPolygonsDataFrame then block Kriging predictions are computed, otherwise point Kriging predictions.

type

character keyword defining what target quantity should be predicted (computed). Possible values are

- "signal": the "signal" $Z(s) = x(s)^{T}\beta + B(s)$ of the process (default),
- "response": the observations $Y(s) = Z(s) + \varepsilon(s)$,

• "trend": the external drift $x(s)^{\mathrm{T}}\beta$,

• "terms": the model terms.

terms If type = "terms", which terms (default is all terms).

se.fit logical, only used if type is equal to "terms", see predict.lm.

signif positive numeric equal to the tolerance or confidence level for computing re-

spective intervals. If NULL no intervals are computed.

locations an optional one-sided formula specifying what variables of newdata are the co-

ordinates of the prediction points

(default: object[["locations.objects"]][["locations"]]).

variogram.model

an optional character keyword defining the variogram model to be used for Krig-

ing, see georob and Details.

param an optional named numeric vector with values of the variogram parameters used

for Kriging, see georob and Details.

an iso an optional named numeric vector with values of anisotropy parameters of a

variogram used for Kriging, see georob and Details.

variogram.object

an optional list that defines a possibly nested variogram model used for Kriging,

see georob and Details.

control a list with the components full.covmat, extended.output, mmax, ncores,

pwidth, pheight, napp and pcmp or a function such as control.predict.georob

that generates such a list.

full.covmat logical controlling whether the full covariance matrix of the prediction errors is

returned (TRUE) or only the vector with its diagonal elements (FALSE, default),

see Value for an explanation of the effect of full.covmat.

extended.output

logical controlling whether the covariance matrices of the Kriging predictions

and of the data should be computed, see *Details* (default FALSE).

mmax integer equal to the maximum number (default 10000) of prediction items, com-

puted in a sub-task, see Details.

ncores positive integer controlling how many cores are used for parallelized computa-

tions, see Details.

pwidth, pheight, napp

numeric scalars, used to tune numeric integration of semi-variances for block

Kriging, see preCKrige.

pcmp a list of arguments passed to pmm or a function such as control.pcmp that gen-

erates such a list (see control.pcmp for allowed arguments).

verbose positive integer controlling logging of diagnostic messages to the console.

verbose = 0 (default) largely suppresses such messages.

... arguments passed to control.predict.georob.

Details

If newdata is an object of class SpatialPoints, SpatialPixels or SpatialGrid then the drift model may only use the coordinates as covariates (universal Kriging). Furthermore the names used for the coordinates in newdata must be the same as in data when creating object (argument locations of predict.georob should not be used). Note that the result returned by predict.georob is then an object of class SpatialPointsDataFrame, SpatialPixelsDataFrame or SpatialGridDataFrame.

The predict method for class georob uses the packages **parallel**, **snow** and **snowfall** for parallelized computation of Kriging predictions. If there are m items to predict, the task is split into ceiling(m/mmax) sub-tasks that are then distributed to ncores CPUs. Evidently, ncores = 1 suppresses parallel execution. By default, the function uses all available CPUs as returned by detectCores.

Note that if full.covmat is TRUE mmax must exceed m (and parallel execution is not possible).

The argument extended.output = TRUE is used to compute all quantities required for (approximately) unbiased back-transformation of Kriging predictions of log-transformed data to the original scale of the measurements by lgnpp. In more detail, the following items are computed:

- trend: the fitted values, $x(s)^{\mathrm{T}}\widehat{\beta}$,
- var. pred: the variances of the Kriging predictions, $\operatorname{Var}_{\hat{\theta}}[\widehat{Y}(s)]$ or $\operatorname{Var}_{\hat{\theta}}[\widehat{Z}(s)]$,
- cov.pred.target: the covariances between the predictions and the prediction targets, $\operatorname{Cov}_{\hat{\theta}}[\widehat{Y}(s),Y(s)]$ or $\operatorname{Cov}_{\hat{\theta}}[\widehat{Z}(s),Z(s)]$,
- var. target: the variances of the prediction targets $\operatorname{Var}_{\hat{a}}[Y(s)]$ or $\operatorname{Var}_{\hat{a}}[Z(s)]$.

Note that the component var.pred is also present if type is equal to "trend", irrespective of the choice for extended.output. This component contains then the variances of the fitted values.

Value

If type is equal to "terms" then a vector, a matrix, or a list with prediction results along with bounds and standard errors, see predict.lm. Otherwise, the structure and contents of the output generated by predict.georob are determined by the class of newdata and the logical flags full.covmat and extended.output:

If full.covmat is FALSE then the result is an object of a "similar" class as newdata (data frame, SpatialPointsDataFrame, SpatialPixelsDataFrame SpatialGridDataFrame, SpatialPolygonsDataFrame).

The data frame or the data slot of the Spatial...DataFrame objects have the following components:

- the coordinates of the prediction points (only present if newdata is a data frame).
- pred: the Kriging predictions (or fitted values).
- se: the root mean squared prediction errors (Kriging standard errors).
- lower, upper: the limits of tolerance/confidence intervals,
- trend, var.pred, cov.pred.target, var.target: only present if extended.output is TRUE, see *Details*.

If full.covmat is TRUE then predict.georob returns a list with the following components:

- pred: a data frame or a Spatial...DataFrame object as described above for full.covmat = FALSE.
- mse.pred: the full covariance matrix of the prediction errors, $Y(s) \hat{Y}(s)$ or $Z(s) \hat{Z}(s)$ see *Details*.
- var.pred: the full covariance matrix of the Kriging predictions, see *Details*.
- cov.pred.target: the full covariance matrix of the predictions and the prediction targets, see Details.
- var.target: the full covariance matrix of the prediction targets, see *Details*.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Nussbaum, M., Papritz, A., Baltensweiler, A. and Walthert, L. (2014) Estimating soil organic carbon stocks of Swiss forest soils by robust external-drift kriging. *Geoscientific Model Development*, 7, 1197–1210. doi: 10.5194/gmd711972014, https://gmd.copernicus.org/articles/7/1197/2014/.

Künsch, H. R., Papritz, A., Schwierz, C. and Stahel, W. A. (2011) Robust estimation of the external drift and the variogram of spatial data. Proceedings of the ISI 58th World Statistics Congress of the International Statistical Institute. doi: 10.3929/ethza009900710

See Also

variograms.

```
georobIntro for a description of the model and a brief summary of the algorithms;
georob for (robust) fitting of spatial linear models;
georobObject for a description of the class georob;
profilelogLik for computing profiles of Gaussian likelihoods;
plot.georob for display of RE(ML) variogram estimates;
control.georob for controlling the behaviour of georob;
georobModelBuilding for stepwise building models of class georob;
cv.georob for assessing the goodness of a fit by georob;
georobMethods for further methods for the class georob;
lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data;
georobSimulation for simulating realizations of a Gaussian process from model fitted by georob;
and finally
sample.variogram and fit.variogram.model for robust estimation and modelling of sample
```

64 profilelogLik

Examples

```
## Not run:
data(meuse)
data(meuse.grid)
coordinates(meuse.grid) <- ~x+y</pre>
meuse.grid.pixdf <- meuse.grid</pre>
gridded(meuse.grid.pixdf) <- TRUE</pre>
library(constrainedKriging)
data(meuse.blocks)
r.logzn.rob <- georob(log(zinc) \sim sqrt(dist), data = meuse, locations = \sim x + y,
    variogram.model = "RMexp", param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1., control = control.georob(cov.bhat = TRUE, full.cov.bhat = TRUE))
## point predictions of log(Zn)
r.pred.points <- predict(r.logzn.rob, newdata = meuse.grid.pixdf,</pre>
    control = control.predict.georob(extended.output = TRUE, full.covmat = TRUE))
str(r.pred.points$pred@data)
## back-transformation of point predictions
r.backtf.pred.points <- lgnpp(r.pred.points)</pre>
str(r.pred.points$pred@data)
spplot(r.backtf.pred.points[["pred"]], zcol = "lgn.pred", main = "Zn content")
## predicting mean Zn content for whole area
r.block <- lgnpp(r.pred.points, is.block = TRUE, all.pred = r.backtf.pred.points[["pred"]])</pre>
r.block
## block predictions of log(Zn)
r.pred.block <- predict(r.logzn.rob, newdata = meuse.blocks,</pre>
    control = control.predict.georob(extended.output = TRUE,
        pwidth = 75, pheight = 75)
r.backtf.pred.block <- lgnpp(r.pred.block, newdata = meuse.grid)</pre>
spplot(r.backtf.pred.block, zcol = "lgn.pred", main = "block means Zn content")
## End(Not run)
```

profilelogLik

Profile Likelihood

Description

The function profilelogLik computes for an array of fixed variogram parameters the profile log-likelihood by maximizing the (restricted) log-likelihood with respect to the remaining variogram parameters, the fixed and random effects.

profilelogLik 65

Usage

```
profilelogLik(object, values, use.fitted = TRUE, verbose = 0,
    ncores = min(detectCores(), NROW(values)))
```

Arguments

object an object of class "georob" (mandatory argument), see georobObject.

values a data.frame or a matrix with the values of the variogram and anisotropy parameters that should be kept fixed (mandatory argument, see georob and georobIntro for information about the parametrization of variogram models). The names of the columns of values must match the names of variogram and anisotropy parameters.

use.fitted logical scalar controlling whether the fitted variogram parameters of object should be used as initial values (default TRUE) when maximizing the profile log-likelihood or the initial values used to generate object.

verbose positive integer controlling logging of diagnostic messages to the console during model fitting, see georob.

positive integer controlling how many cores are used for parallelized computa-

tions, see Details.

Details

ncores

For robust REML fits profilelogLik returns (possibly with a warning) the log-likelihood of the Gaussian (RE)ML fit of the equivalent Gaussian spatial linear model with heteroscedastic nugget.

Note that the data frame passed as data argument to georob must exist in the user workspace when calling profilelogLik.

profilelogLik uses the packages **parallel**, **snow** and **snowfall** for parallelized computation of the profile likelihood. By default, the function uses NROW(values) CPUs but not more than are physically available (as returned by detectCores).

profilelogLik uses the function update to re-estimated the model with partly fixed variogram parameters. Therefore, any argument accepted by georob except data can be changed when refitting the model. Some of them (e.g. verbose) are explicit arguments of profilelogLik, but also the remaining ones can be passed by . . . to the function.

Value

A data.frame with the columns of values, a column loglik (contains the maximized [restricted] log-likelihood), columns with the estimated variogram and fixed effect parameters, columns with the gradient of the (restricted) log-likelihood (or the roots of the estimating equations) and a column converged, indicating whether convergence has occurred converged ==1 when fitting the respective model.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms; georob for (robust) fitting of spatial linear models; georobObject for a description of the class georob; plot.georob for display of RE(ML) variogram estimates; control.georob for controlling the behaviour of georob; georobModelBuilding for stepwise building models of class georob; cv.georob for assessing the goodness of a fit by georob; georobMethods for further methods for the class georob; predict.georob for computing robust Kriging predictions; lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data; georobSimulation for simulating realizations of a Gaussian process from model fitted by georob; and finally sample.variogram and fit.variogram.model for robust estimation and modelling of sample variograms.
```

Examples

```
## Not run:
data(meuse)

r.logzn.ml <- georob(log(zinc)~sqrt(dist), data=meuse, locations=~x+y,
    variogram.model="RMexp", param=c(variance=0.15, nugget=0.05, scale=200),
    tuning.psi=1000, control=control.georob(ml.method="ML"))

r.prflik <- profilelogLik(r.logzn.ml, values=expand.grid(scale=seq(75, 600, by=25)), ncores = 1)
## using multiple cores
## r.prflik <- profilelogLik(r.logzn.ml, values=expand.grid(scale=seq(75, 600, by=25)))
plot(loglik~scale, r.prflik, type="1")
abline(v=r.logzn.ml$variogram.object[[1]]$param["scale"], lty="dotted")
abline(h=r.logzn.ml$loglik-0.5*qchisq(0.95, 1), lty="dotted")

## End(Not run)</pre>
```

 ${\tt sample.variogram}$

Computing (Robust) Sample Variograms of Spatial Data

Description

The function sample.variogram computes the sample (empirical) variogram of a spatial variable by the method-of-moment and three robust estimators. Both omnidirectional and direction-dependent variograms can be computed, the latter for observation locations in a three-dimensional domain. There are summary and plot methods for summarizing and displaying sample variograms.

Usage

```
sample.variogram(object, ...)
## Default S3 method:
sample.variogram(object, locations, lag.dist.def,
   xy.angle.def = c(0, 180), xz.angle.def = c(0, 180), max.lag = Inf,
   estimator = c("qn", "mad", "matheron", "ch"), mean.angle = TRUE, ...)
## S3 method for class 'formula'
sample.variogram(object, data, subset, na.action,
   locations, lag.dist.def, xy.angle.def = c(0, 180),
   xz.angle.def = c(0, 180), max.lag = Inf,
   estimator = c("qn", "mad", "matheron", "ch"), mean.angle = TRUE, ...)
## S3 method for class 'georob'
sample.variogram(object, lag.dist.def,
   xy.angle.def = c(0, 180), xz.angle.def = c(0, 180), max.lag = Inf,
   estimator = c("qn", "mad", "matheron", "ch"), mean.angle = TRUE, ...)
## S3 method for class 'sample.variogram'
summary(object, ...)
## S3 method for class 'sample.variogram'
plot(x, type = "p", add = FALSE,
   xlim = c(0, max(x[["lag.dist"]])),
   ylim = c(0, 1.1 * max(x[["gamma"]])), col, pch, lty, cex = 0.8,
   xlab = "lag distance", ylab = "semivariance",
   annotate.npairs = FALSE, npairs.pos = 3, npairs.cex = 0.7,
   legend = nlevels(x[["xy.angle"]]) > 1 || nlevels(x[["xz.angle"]]) > 1,
   legend.pos = "topleft", ...)
```

Arguments

object a numeric vector with the values of the response for which the sample vari-

ogram should be computed (sample.variogram.default), a formula, specifying in its left part the response variable (right part of formula is ignored,

sample.variogram.formula), an object of class georob (sample.variogram.georob) or an object of class

sample.variogram (summary.sample.variogram).

locations a numeric matrix with the coordinates of the locations where the response was

observed (sample.variogram.default) or a one-sided formula specifying the coordinates (sample.variogram.formula). The matrix may have an arbitrary number of columns for an omnidirectional variogram, but at most 3 columns if

a directional variogram is computed.

data an optional data frame, list or environment (or another object coercible by

as.data.frame to a data frame) containing the response variable and the co-

ordinates where the data was recorded. If not found in data, the variables are taken from environment (formula), typically the environment from which sample.variogram is called. subset an optional vector specifying a subset of observations to be used for estimating the variogram. a function which indicates what should happen when the data contain NAs. The na.action default is set by the na. action argument of options, and is na. fail if that is unset. The "factory-fresh" default is na.omit. Another possible value is NULL, no action. Value na. exclude can be useful. a numeric scalar defining a constant bin width for grouping the lag distances or lag.dist.def a numeric vector with the bounds of a set of contiguous bins (upper bounds of bins except for the first element of lag.dist.def which is the lower bound of the first bin). This argument is mandatory. xy.angle.def an numeric vector defining angular classes in the horizontal plane for computing directional variograms. xy.angle.def must contain an ascending sequence of azimuth angles in degrees from north (positive clockwise to south), see Details. Omnidirectional variograms are computed with the default c(0,180). xz.angle.def an numeric vector defining angular classes in the x-z-plane for computing directional variograms. xz.angle.def must contain an ascending sequence of angles in degrees from zenith (positive clockwise to nadir), see *Details*. Omnidirectional variograms are computed with the default c(0,180). max.lag positive numeric defining the largest lag distance for which semi variances should be computed (default no restriction). character keyword defining the estimator for computing the sample variogram. estimator Possible values are: • "gn": Genton's robust On-estimator (default, Genton, 1998), • "mad": Dowd's robust MAD-estimator (Dowd, 1984), • "matheron": non-robust method-of-moments estimator, • "ch": robust Cressie-Hawkins estimator (Cressie and Hawkins, 1980). mean.angle logical controlling whether the mean lag vector (per combination of lag distance and angular class) is computed from the mean angles of all the lag vectors falling into a given class (TRUE, default) or from the mid-angles of the respective angular classes (FALSE). an object of class sample.variogram. type, xlim, ylim, xlab, ylab see respective arguments of plot.default. add logical controlling whether a new plot should be generated (FALSE, default) or whether the information should be added to the current plot (TRUE). col the color of plotting symbols for distinguishing semi variances for angular classes in the x-y-plane.

the type of plotting symbols for distinguishing semi variances for angular classes

pch

lty

in the x-z-plane. the line type.

	cex	character expansion factor for plotting symbols.
annotate.npairs		
		logical controlling whether the plotting symbols should be annotated by the number of data pairs per lag class.
	npairs.pos	integer defining the position where text annotation about number of pairs should be plotted, see $text$.
	npairs.cex	numeric defining the character expansion for text annotation about number of pairs.
	legend	logical controlling whether a legend should be plotted.
	legend.pos	a character keyword defining where to place the legend, see ${\tt legend}$ for possible values.
		additional arguments passed to plot, formula.

Details

The angular classes in the x-y- and x-z-plane are defined by vectors of ascending angles on the half circle. The ith angular class is defined by the vector elements, say I and u, with indices i and i+1. A lag vector belongs to the ith angular class if its azimuth (or angle from zenith), say φ , satisfies $l < \varphi \le u$. If the first and the last element of xy.angle.def or xz.angle.def are equal to 0 and 180 degrees, respectively, then the first and the last angular class are "joined", i.e., if there are K angles, there will be only K-2 angular classes and the first class is defined by the interval (xy.angle.def[K-1]-180, xy.angle.def[K-1] and the last class by (xy.angle.def[K-2], xy.angle.def[K-1]].

Value

An object of class sample.variogram, which is a data frame with the following components:

lag.dist	the mean lag distance of the lag class,
xy.angle	the angular class in the x - y -plane,
xz.angle	the angular class in the x - z -plane,
gamma	the estimated semi-variance of the lag class,
npairs	the number of data pairs in the lag class,
lag.x	the x -component of the mean lag vector of the lag class,
lag.x	the y-component of the mean lag vector of the lag class,
lag.z	the z-component of the mean lag vector of the lag class.

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Cressie, N. and Hawkins, D. M. (1980) Robust Estimation of the Variogram: I. *Mathematical Geology*, **12**, 115–125.

Dowd, P. A. (1984) The variogram and Kriging: Robust and resistant estimators. In Geostatistics

```
for Natural Resources Characterization, Verly, G., David, M., Journel, A. and Marechal, A. (Eds.) Dordrecht: D. Reidel Publishing Company, Part I, 1, 91–106.
```

Genton, M. (1998) Highly Robust Variogram Estimation. *Mathematical Geology*, **30**, 213–220.

See Also

```
georobIntro for a description of the model and a brief summary of the algorithms;
georob for (robust) fitting of spatial linear models;
georobObject for a description of the class georob;
profilelogLik for computing profiles of Gaussian likelihoods;
plot.georob for display of RE(ML) variogram estimates;
control.georob for controlling the behaviour of georob;
georobModelBuilding for stepwise building models of class georob;
cv.georob for assessing the goodness of a fit by georob;
georobMethods for further methods for the class georob;
predict.georob for computing robust Kriging predictions;
lgnpp for unbiased back-transformation of Kriging prediction of log-transformed data;
georobSimulation for simulating realizations of a Gaussian process from model fitted by georob.
```

Examples

validate.predictions Summary Statistics of (Cross-)Validation Prediction Errors

Description

Functions to compute and plot summary statistics of prediction errors to (cross-)validate fitted spatial linear models by the criteria proposed by Gneiting et al. (2007) for assessing probabilistic forecasts.

Usage

```
validate.predictions(data, pred, se.pred,
    statistic = c("crps", "pit", "mc", "bs", "st"), ncutoff = NULL)
## S3 method for class 'cv.georob'
plot(x,
    type = c("sc", "lgn.sc", "ta", "qq", "hist.pit", "ecdf.pit", "mc", "bs"),
    smooth = TRUE, span = 2/3, ncutoff = NULL, add = FALSE,
    col, pch, lty, main, xlab, ylab, ...)
## S3 method for class 'cv.georob'
print(x, digits = max(3, getOption("digits") - 3), ...)
## S3 method for class 'cv.georob'
summary(object, se = FALSE, ...)
```

Arguments

data	a numeric vector with observations about a response (mandatory argument).
pred	a numeric vector with predictions for the response (mandatory argument).
se.pred	a numeric vector with prediction standard errors (mandatory argument).
statistic	character keyword defining what statistic of the prediction errors should be computed. Possible values are (see <i>Details</i>):
	 "crps": continuous ranked probability score (default), "pit": probability integral transform, "mc": average predictive distribution (marginal calibration), "bs": Brier score, "st": mean and dispersion statistics of (standardized) prediction errors.
ncutoff	positive integer (N) giving the number of quantiles, for which CDFs are evaluated (type = "mc"), or the number of thresholds for which the Brier score is computed (type = "bs"), see $Details$ (default: min(500,length(data))).
x, object	objects of class cv.georob.

digits

positive integer indicating the number of decimal digits to print.

type

character keyword defining what type of plot is created by the plot.cv.georob. Possible values are:

- "sc": a scatter-plot of the (possibly log-transformed) response vs. the respective predictions (default).
- "lgn.sc": a scatter-plot of the untransformed response against backtransformed predictions of the log-transformed response.
- "ta": Tukey-Anscombe plot (plot of standardized prediction errors vs. predictions).
- "qq": normal QQ plot of standardized prediction errors.
- "hist.pit": histogram of probability integral transform, see *Details*.
- "ecdf.pit": empirical CDF of probability integral transform, see *Details*.
- "mc": a marginal calibration plot, see *Details*,
- "bs": a plot of Brier score vs. threshold, see *Details*.

smooth

control whether scatter plots of data vs. predictions should be smoothed by loess.smooth.

span

smoothness parameter for loess (see loess.smooth).

add

logical controlling whether the current high-level plot is added to an existing graphics without cleaning the frame before (default: FALSE).

main, xlab, ylab

title and axes labels of plot.

col, pch, lty

color, symbol and line type.

se

logical controlling if the standard errors of the averaged continuous ranked probability score and of the mean and dispersion statistics of the prediction errors (see Details) are computed from the respective values computed for the K cross-validation subsets (default, EALSE)

validation subsets (default: FALSE).

. . .

additional arguments passed to the methods.

Details

validate.predictions computes the items required to evaluate (and plot) the diagnostic criteria proposed by Gneiting et al. (2007) for assessing the *calibration* and the *sharpness* of probabilistic predictions of (cross-)validation data. To this aim, validate.predictions uses the assumption that the prediction errors $Y(s) - \widehat{Y}(s)$ follow normal distributions with zero mean and standard deviations equal to the Kriging standard errors. This assumption is an approximation if the errors ε come from a long-tailed distribution. Furthermore, for the time being, the Kriging variance of the *response* Y is approximated by adding the estimated nugget $\widehat{\tau}^2$ to the Kriging variance of the signal Z. This approximation likely underestimates the mean squared prediction error of the response if the errors come from a long-tailed distribution. Hence, for robust Kriging, the standard errors of the (cross-)validation errors are likely too small.

Notwithstanding these difficulties and imperfections, validate.predictions computes

• the probability integral transform (PIT),

where $F_i(y_i)$ denotes the (plug-in) predictive CDF evaluated at y_i , the value of the *i*th (cross-)validation datum,

• the average predictive CDF (plug-in)

$$\bar{F}_n(y) = 1/n \sum_{i=1}^n F_i(y),$$

where n is the number of (cross-)validation observations and the F_i are evaluated at N quantiles equal to the set of distinct y_i (or a subset of size N of them),

• the Brier Score (plug-in)

BS(y) =
$$1/n \sum_{i=1}^{n} (F_i(y) - I(y_i \le y))^2$$
,

where I(x) is the indicator function for the event x, and the Brier score is again evaluated at the unique values of the (cross-)validation observations (or a subset of size N of them),

• the *averaged continuous ranked probability score*, CRPS, a strictly proper scoring criterion to rank predictions, which is related to the Brier score by

$$CRPS = \int_{-\infty}^{\infty} BS(y) \, dy.$$

Gneiting et al. (2007) proposed the following plots to validate probabilistic predictions:

- A histogram (or a plot of the empirical CDF) of the PIT values. For ideal predictions, with observed coverages of prediction intervals matching nominal coverages, the PIT values have an uniform distribution.
- Plots of $\bar{F}_n(y)$ and of the empirical CDF of the data, say $\widehat{G}_n(y)$, and of their difference, $\bar{F}_n(y) \widehat{G}_n(y)$ vs y. The forecasts are said to be *marginally calibrated* if $\bar{F}_n(y)$ and $\widehat{G}_n(y)$ match.
- A plot of BS(y) vs. y. Probabilistic predictions are said to be *sharp* if the area under this curve, which equals CRPS, is minimized.

The plot method for class cv.georob allows to create these plots, along with scatter-plots of observations and predictions, Tukey-Anscombe and normal QQ plots of the standardized prediction errors.

summary.cv.georob computes the mean and dispersion statistics of the (standardized) prediction errors (by a call to validate.prediction with argument statistic = "st", see Value) and the averaged continuous ranked probability score (crps). If present in the cv.georob object, the error statistics are also computed for the errors of the unbiasedly back-transformed predictions of a log-transformed response. If se is TRUE then these statistics are evaluated separately for the Value K cross-validation subsets and the standard errors of the means of these statistics are returned as well.

The print method for class cv. georob returns the mean and dispersion statistics of the (standard-ized) prediction errors.

Value

Depending on the argument statistic, the function validate.predictions returns

- a numeric vector of PIT values if statistic is equal to "pit",
- a named numeric vector with summary statistics of the (standardized) prediction errors if statistic is equal to "st". The following statistics are computed:

```
me mean prediction error
mede median prediction error
rmse root mean squared prediction error
made median absolute prediction error
qne Qn dispersion measure of prediction errors (see Qn)
msse mean squared standardized prediction error
medsse median squared standardized prediction error
```

- a data frame if statistic is equal to "mc" or "bs" with the components (see *Details*):
- z the sorted unique (cross-)validation observations (or a subset of size ncutoff of them)

```
ghat the empirical CDF of the (cross-)validation observations \widehat{G}_n(y) the average predictive distribution \overline{F}_n(y) bs the Brier score \mathrm{BS}(y)
```

Author(s)

Andreas Papritz <andreas.papritz@env.ethz.ch>.

References

Gneiting, T., Balabdaoui, F. and Raftery, A. E.(2007) Probabilistic forecasts, calibration and sharpness. *Journal of the Royal Statistical Society Series B* **69**, 243–268.

See Also

```
georob for (robust) fitting of spatial linear models;cv.georob for assessing the goodness of a fit by georob.
```

Examples

```
## Not run:
data(meuse)

r.logzn <- georob(log(zinc) ~ sqrt(dist), data = meuse, locations = ~ x + y,
    variogram.model = "RMexp",
    param = c(variance = 0.15, nugget = 0.05, scale = 200),
    tuning.psi = 1)

r.logzn.cv.1 <- cv(r.logzn, seed = 1, lgn = TRUE, ncores = 1, verbose = 1)</pre>
```

wolfcamp 75

```
r.logzn.cv.2 <- cv(r.logzn, formula = .~. + ffreq, seed = 1, lgn = TRUE,
   ncores = 1, verbose = 1)
summary(r.logzn.cv.1, se = TRUE)
summary(r.logzn.cv.2, se = TRUE)
op \leftarrow par(mfrow = c(2,2))
plot(r.logzn.cv.1, type = "lgn.sc")
plot(r.logzn.cv.2, type = "lgn.sc", add = TRUE, col = "red")
abline(0, 1, lty= "dotted")
plot(r.logzn.cv.1, type = "ta")
plot(r.logzn.cv.2, type = "ta", add = TRUE, col = "red")
abline(h=0, lty= "dotted")
plot(r.logzn.cv.2, type = "mc", col = "red")
plot(r.logzn.cv.1, type = "bs")
plot(r.logzn.cv.2, type = "bs", add = TRUE, col = "red")
legend("topright", lty = 1, col = c("black", "red"), bty = "n",
    legend = c("log(Zn) ~ sqrt(dist)", "log(Zn) ~ sqrt(dist) + ffreq"))
par(op)
## End(Not run)
```

wolfcamp

Wolfcamp Aquifer Data

Description

Piezometric head measurements taken at the Wolfcamp Aquifer, Texas, USA. See *Cressie* (1993, p. 212–214) for description of the scientific problem and the data. Original data were converted to SI units: coordinates are given in kilometers and pressure heads in meters.

Usage

```
data(wolfcamp)
```

Format

A data frame with 85 observations on the following 3 variables:

x a numeric vector with the easting coordinate in kilometers.

y a numeric vector with the northing coordinate in kilometers.

pressure a numeric vector with the piezometric head in meters.

Note

The data were imported from the package **geoR**.

76 wolfcamp

Source

Harper, W.V. and Furr, J.M. (1986) Geostatistical analysis of potentiometric data in the Wolfcamp Aquifer of the Palo Duro Basin, Texas. *Technical Report BMI/ONWI-587*, *Bettelle Memorial Institute*, *Columbus*, *OH*.

References

Cressie, N.A.C (1993) Statistics for Spatial Data. New York: Wiley.

Papritz, A. and Moyeed, R. (2001) Parameter uncertainty in spatial prediction: checking its importance by cross-validating the Wolfcamp and Rongelap data sets. *GeoENV 2000: Geostatistical for Environmental Applications. Ed. P. Monestiez, D. Allard, R. Froidevaux.* Kluwer.

Examples

data(wolfcamp)
summary(wolfcamp)

Index

* datasets	georobS3methods,41
elevation, 16	georobSimulation, 45
wolfcamp, 75	1gnpp, 49
* methods	param.names, 54
georobS3methods, 41	plot.georob, 55
* models	pmm, 58
compress, 2	predict.georob, 60
control.georob, 3	profilelogLik,64
cv, 9	sample.variogram,66
cv.georob, 10	validate.predictions, 71
default.aniso, 15	* spatial
fit.variogram.model, 17	compress, 2
georob, 23	control.georob, 3
georobModelBuilding, 30	cv, 9
georobObject, 34	cv.georob, 10
georobPackage, 37	default.aniso, 15
georobS3methods, 41	fit.variogram.model, 17
georobSimulation, 45	georob, 23
1gnpp, 49	georobModelBuilding, 30
param.names, 54	georobObject, 34
plot.georob, 55	georobPackage, 37
pmm, 58	georobS3methods, 41
predict.georob, 60	georobSimulation, 45
profilelogLik,64	lgnpp, 49
sample.variogram, 66	param.names, 54
validate.predictions, 71	plot.georob, 55
* package	pmm, 58
georobPackage, 37	predict.georob, 60
* print	profilelogLik, 64
georobS3methods, 41	sample.variogram, 66
* robust	validate.predictions,71
compress, 2	add1.georob, 40
control.georob, 3	add1.georob(georobModelBuilding), 30
default.aniso, 15	as.data.frame, 24, 67
fit.variogram.model, 17	27, 37
georob, 23	bwd.transf, 20
georobModelBuilding, 30	<pre>bwd.transf(control.georob), 3</pre>
georobObject, 34	
georobPackage, 37	<pre>coef.georob(georobS3methods), 41</pre>

78 INDEX

compress, 2, 35, 47	fixef(georobS3methods),41
condsim (georobSimulation), 45	formula, 24, 31, 42, 43
confint, 43	fwd.transf, 20
<pre>control.condsim(georobSimulation), 45</pre>	<pre>fwd.transf(control.georob), 3</pre>
control.fit.variogram.model	
(fit.variogram.model), 17	georob, 3, 5, 8–14, 16, 18, 21, 22, 23, 32–34,
control.georob, 3, 14, 19, 20, 22, 26–29, 33,	36, 40, 44–48, 53–55, 57, 59, 61, 63,
35, 36, 40, 44, 48, 57, 63, 66, 70	65, 66, 70, 74
control.nleqslv(control.georob), 3	georobIntro, 9, 14, 16, 18, 21, 22, 24–26, 28,
control.nlminb, 20	33, 34, 36, 44, 46–48, 51, 53–55, 57,
<pre>control.nlminb (control.georob), 3</pre>	59, 63, 65, 66, 70
control.optim, 20, 27	georobIntro(georobPackage), 37
<pre>control.optim(control.georob), 3</pre>	georobMethods, 9, 14, 22, 29, 33, 34, 36, 41,
control.pcmp, 7, 47, 61	48, 57, 63, 66, 70
control.pcmp (pmm), 58	<pre>georobMethods (georobS3methods), 41</pre>
control.predict.georob, 40	georobModelBuilding, 9, 14, 22, 29, 30, 34,
control.predict.georob	36, 40, 44, 48, 57, 63, 66, 70
(predict.georob), 60	georobObject, 9, 11, 14, 22, 28, 31–33, 34,
control.rq(control.georob), 3	40, 42, 44, 45, 48, 55, 57, 60, 63, 65,
cv, 9	66, 70
cv.georob, 9, 10, 10, 22, 29, 33, 34, 36, 40,	georobPackage, 32, 37
41, 44, 48, 57, 63, 66, 70, 74	georobS3methods, 41
	georobSimulation, 9, 14, 22, 29, 33, 37, 41,
default.aniso, 15, 18, 25, 26	44, 45, 57, 63, 66, 70
default.fit.aniso, <i>19</i> , <i>25</i> , <i>26</i>	
default.fit.aniso(default.aniso), 15	kmeans, 11
default.fit.param, 18, 25, 26	
default.fit.param(default.aniso), 15	legend, 69
detectCores, 13, 48, 62, 65	lgnpp, 9, 14, 22, 29, 33, 37, 40, 41, 44, 48, 49,
deviance.georob, 40	57, 62, 63, 66, 70
deviance.georob(georobModelBuilding),	lines.fitted.variogram
30	(fit.variogram.model), 17
df.residual, 43	lines.georob(plot.georob), 55
dfwd.transf(control.georob),3	lm, 5, 24, 27, 36
drop1.georob, 40	1mrob, 5, 27, 28, 36
drop1.georob(georobModelBuilding), 30	lmrob.control, 7, 36
1 16	loess.smooth, 56, 57, 72
elevation, 16	logLik.georob, 40
expand, 35	logLik.georob(georobModelBuilding), 30
expand (compress), 2	madal frame manula (manula C2mathada) 41
extractAIC, 31	model.frame.georob(georobS3methods), 41
extractAIC.georob, 40	model.matrix.default, 24
extractAIC.georob	<pre>model.matrix.georob(georobS3methods),</pre>
(georobModelBuilding), 30	41
fit.variogram.model, 9, 14, 17, 29, 33, 37,	na.exclude, <i>24</i> , <i>68</i>
40, 41, 44, 48, 57, 63, 66	na.fail, <i>24</i> , <i>68</i>
fitted, <i>43</i>	na.omit, <i>24</i> , <i>68</i>
fixed.effects(georobS3methods), 41	nleasly, 7, 8, 26-28, 35, 39

INDEX 79

nlminb, 5, 7, 8, 20, 26, 28, 35, 39	random.effects (georobS3methods), 41
nobs.georob(georobS3methods), 41	ranef (georobS3methods), 41
numericDeriv, 39	ranef.georob, 40
	resid.georob(georobS3methods),41
offset, 24	residuals.georob, 40
optim, 5, 7, 8, 20, 21, 26–28, 35, 39	residuals.georob(georobS3methods),41
options, 24, 68	residuals.lm,42
	RFsimulate, 47
param.bounds, 27	RMmodel, 15, 18, 24-27, 39
param.bounds (param.names), 54	rq, 5, 7, 8, 27, 36
param.names, 15, 18, 25, 26, 54	rstandard.georob, 40
param.transf, 20	rstandard.georob(georobS3methods),41
param.transf(control.georob), 3	runif, <i>11</i>
plot, <i>57</i>	
plot.cv.georob(validate.predictions),	sample.variogram, 9, 14, 18, 29, 33, 37, 40,
71	41, 44, 48, 56, 57, 63, 66, 66
plot.default, 68	set.seed, 11, 45
plot.formula, 69	SpatialGrid, 45, 60
plot.georob, 9, 14, 22, 29, 33, 34, 36, 40, 44,	SpatialGridDataFrame, 45, 48, 60, 62
48, 55, 63, 66, 70	SpatialPixels, 45, 60
plot.lmrob, 56, 57	SpatialPixelsDataFrame, 45, 48, 60, 62
plot.sample.variogram, 57	SpatialPoints, 45, 60
plot.sample.variogram	SpatialPointsDataFrame, 24, 45, 48, 60, 62
(sample.variogram), 66	SpatialPolygonsDataFrame, 48, 51, 60, 62
pmm, 7, 47, 58, 61	step, 30–32
preCKrige, 61	step (georobModelBuilding), 30
predict, 50	step.georob, 40
predict.georob, 9, 14, 22, 29, 33, 34, 37, 40,	summary.cv.georob
41, 44, 45, 48, 50, 52, 53, 57, 60, 66,	(validate.predictions), 71
70	summary.fitted.variogram
predict.lm, 61, 62	(fit.variogram.model), 17
print.coef.georob(georobS3methods), 41	summary.georob, 36 summary.georob(georobS3methods), 41
<pre>print.cv.georob(validate.predictions),</pre>	summary.sample.variogram
	(sample.variogram), 66
<pre>print.fitted.variogram (fit.variogram.model), 17</pre>	(Sample: var logi am), 00
	termplot, $43,60$
print.georob (georobS3methods), 41	terms, 42
<pre>print.summary.cv.georob (validate.predictions),71</pre>	text, 69
print.summary.fitted.variogram	
(fit.variogram.model), 17	update, <i>11–13</i> , <i>43</i> , <i>65</i>
print.summary.georob(georobS3methods),	
41	validate.predictions, 10 , 14 , 40 , 71
print.summary.sample.variogram	vcov.georob(georobS3methods),41
(sample.variogram), 66	1 1/2 / 21 22
profilelogLik, 9, 14, 22, 28, 33, 36, 40, 44,	waldtest, 31, 32
48, 57, 63, 64, 70	waldtest (georobModelBuilding), 30
10, 57, 05, 01, 70	waldtest.georob, 40
Qn, 56, 68, 74	wolfcamp, 75