Package 'snowFT'

June 18, 2017

Title Fault Tolerant Simple Network of Workstations

Version 1.6-0
Date 2017-06-17
Author Hana Sevcikova, A. J. Rossini
Description Extension of the snow package supporting fault tolerant and reproducible applications, as well as supporting easy-to-use parallel programming - only one function is needed. Dynamic cluster size is also available.
Maintainer Hana Sevcikova <hanas@uw.edu></hanas@uw.edu>
License GPL (>= 2)
Imports parallel, snow (>= 0.4)
Depends R ($>= 3.0-0$), rlecuyer
Suggests Rmpi
<pre>URL http://www.stat.washington.edu/hana/parallel/snowFT-doc.pdf</pre>
NeedsCompilation no
Repository CRAN
Date/Publication 2017-06-17 23:50:20 UTC
R topics documented: snowFT-package
snowFT-rand
Index 10

2 snowFT-package

snowFT-package

Fault Tolerant Simple Network of Workstations

Description

Extension of the snow package supporting fault tolerant and reproducible applications, dynamic cluster resizing, as well as supporting easy-to-use parallel programming - only one function is needed. It supports the MPI and the socket communication layers.

Details

Package: snowFT Version: 1.6-0 License: GPL

The main function of this package, performParallel, handles all tasks that are necessary for evaluating a user-defined function in parallel. These include creating a cluster, initializing nodes, handling a random number generator, processing the given function on the cluster and cleaning up. In the very basic settings (i.e. when using with the socket layer), no additional software is necessary. The package can be used on a single multi-processor/core machine, homogeneous cluster, or a heterogeneous group of computers.

The package supports creating and handling a **snow** cluster that is:

- Fault tolerant: The master checks repeatedly for failures in its waiting time and initiates a
 failure recovery if needed. (This feature has been implemented for the PVM layer. Unfortunately, the PVM layer had to be switched off due to the **rpvm** package not being currently
 maintained.)
- 2. Load balanced AND produces reproducible results: one stream of random numbers associated with one replicate (instead of one stream per node as handled by **snow** and **parallel**).
- 3. Computationally transparent: Currently processed replicates and failed replicates stored into files. Allows defining a function that is called after each given number of replicates.
- 4. Dynamically resizeable: The cluster size is stored in a file which is read by the master repeatedly. In case of a modification the cluster is updated. (Not available for MPI.)
- 5. Administration overhead minimized: All administration is managed by the master in its waiting time. (Note that there is a time-overhead for creating and destroying the cluster, as well as the RNG initialization. Thus, simple operations, such as the example below, will not gain from running in parallel.)
- 6. Allows running processes sequentially with the same random numbers as it would in parallel. Thus, results can be compared between the two modes.
- 7. Easy to use: All features, including creating the cluster, RNG initialization and clean-up, are available via one single function performParallel.

Author(s)

Hana Sevcikova, A. J. Rossini

Maintainer: Hana Sevcikova <hanas@uw.edu>

References

http://www.stat.washington.edu/hana/parallel/snowFT-doc.pdf

See Also

```
performParallel, clusterCall
```

Examples

snowFT-cluster

Cluster-Level Functions

Description

Functions that extend the collection of cluster-level functions of the **parallel/snow** package while providing additional features, including reproducibility and dynamic cluster resizing. The heart of the package is the function performParallel.

Usage

```
prngkind = "default", para = 0,
                mngtfiles = c(".clustersize",".proc",".proc_fail"),
                ft_verbose = FALSE, ...)
clusterApplyFT(cl, x, fun, initfun = NULL, initexpr = NULL,
               export = NULL, exitfun = NULL,
               printfun = NULL, printargs = NULL,
               printrepl = max(length(x)/10,1), gentype = "None",
               seed = rep(123456,6), prngkind = "default", para = 0,
               mngtfiles = c(".clustersize", ".proc", ".proc_fail"),
               ft_verbose = FALSE, ...)
clusterCallpart(cl, nodes, fun, ...)
clusterEvalQpart(cl, nodes, expr)
printClusterInfo(cl)
```

Arguments

count Number of cluster nodes. If count=0, the process runs sequentially.

cl Cluster object.

Vector of values to be passed to function fun. Its length determines how many

times fun is to be called. x[i] is passed to fun (as its first argument) in the i-th

call.

fun Function or character string naming a function.

initfun Function or character string naming a function with no arguments that is to be

> called on each node prior to the computation. It is passed to workers using clusterCall. It can be used for example for loading required libraries or sourc-

ing data files.

initexpr Expression evaluated on workers at the time of node initialization. It corre-

sponds to what would be passed to clusterEvalQ before the computation. initfun and initexpr can be used for the same purpose, but initexpr does

not need to have a form of a function.

export Character vector naming objects to be exported to workers.

Function or character string naming a function with no arguments that is to be exitfun

called on each node after the computation is completed.

printfun, printargs, printrepl

printfun is a function or character string naming a function that is to be called on the master node after each printrepl completed replicates, and thus it can be used for accessing intermediate results. Arguments passed to printfun are: a list (of length |x|) of results (including the non-finished ones), the number of

finished results, and printargs.

Character string that specifies cluster type (see makeClusterFT). Possible values

are 'MPI' and 'SOCK' ('PVM' is currently not available).

cltype

cluster.args List of arguments passed to the function makeClusterFT. For the 'SOCK' layer,

the most useful argument in this list is names which can contain a vector of host names, or a list containing specification for each host (see Example in makeCluster). Due to the dynamic resizing feature, the length of this vector (or list) does not need to match the size of the cluster - it is used as a pool from which hosts are taken as they are needed. Another useful argument is outfile,

specifying name of a file to which slave node output is to be directed.

gentype Character string that specifies the type of the random number generator (RNG).

Possible values: "RNGstream" (L'Ecuyer's RNG), "SPRNG", or "None", see

clusterSetupRNG.FT. If gentype="None", no RNG action is taken.

seed, prngkind, para

Seed, kind and parameters for the RNG (see clusterSetupRNG.FT). Seed can

be an integer or a vector of six integers.

mngtfiles A character vector of length 3 containing names of management files: mngtfiles[1]

for managing the cluster size, mngtfiles[2] for monitoring replicates as they are processed, mngtfiles[3] for monitoring failed replicates. If any of these files equals an empty string, the corresponding management actions (i.e. dynamic cluster resizing, outputting processed replicates, and cluster repair in case of failures) are not performed. If the files already exist, their content is overwritten. Note that the cluster repair action was only available for PVM which is switched off. Furthermore, the dynamic cluster resizing is not available for

MPI.

ft_verbose If TRUE, debugging messages are sent to standard output.

nodes Indices of cluster nodes.

expr Expression to evaluate.

... Additional arguments to pass to function fun.

Details

clusterApplyFT is a version of clusterApplyLB of the **parallel/snow** package with additional features, such as results reproducibility, computation transparency and dynamic cluster resizing. The master process does the management in its waiting time.

The file mngtfiles[1] (which defaults to '.clustersize') is initially written by the master prior to the computation and it contains a single integer value corresponding to the number of cluster nodes. The value can be arbitrarily changed by the user (but should remain in the same format). The master reads the file in its waiting time. If the value in this file is larger than the current cluster size, new nodes are created and the computation is expanded on them. If on the other hand the value is smaller, nodes are successively discarded after they finish their current computation. The arguments initfun, initexpr, export and exitfun in the clusterApplyFT function are only used, if there are changes in the cluster, i.e. if new nodes are added or if nodes are removed from cluster.

The RNG uses the scheme 'one stream per replicate', in contrary to 'one stream per node' used by clusterApplyLB. Therefore with each replicate, the RNG is reset to the corresponding stream (identified by the replicate number). Thus, the final results are reproducible regardless of how many nodes were used.

performParallel is a wrapper function for clusterApplyFT and we recommend using this function rather than using clusterApplyFT directly. It creates a cluster of count nodes; on all nodes it calls initfun, evaluates initexpr and export, and initializes the RNG. Then it calls clusterApplyFT. After the computation is finished, it calls exitfun on all nodes and stops the cluster. If count=0, function fun is invoked sequentially with the same settings (including random numbers) as it would in parallel. This mode can be used for debugging purposes.

clusterCallpart calls a function fun with identical arguments . . . on nodes specified by indices nodes in the cluster cl and returns a list of the results.

clusterEvalQpart evaluates a literal expression on nodes specified by indices nodes.

printClusterInfo prints out some basic information about the cluster.

Value

clusterApplyFT returns a list of two elements. The first one is a list (of length |x|) of results, the second one is the (possibly updated) cluster object.

performParallel returns a list of results.

Author(s)

Hana Sevcikova

Examples

```
## Not run:
# generates n normally distributed random numbers in r replicates
# on p nodes and prints their mean after each r/10 replicate.
printfun <- function(res, n, args = NULL) {</pre>
 res <- unlist(res)</pre>
 res <- res[!is.null(res)]</pre>
 print(paste("mean after:", n, "replicates:", mean(res),
           "(from", length(res), "RNs)"))
 }
r <- 1000; n <- 100; p <- 5
res \leftarrow performParallel(p, rep(n,r), fun = rnorm, seed = 1,
                printfun = printfun)
# Setting p <- 0 will run the rnorm call above sequentially and
# should give exactly the same results
res.seq <- performParallel(0, rep(n,r), fun = rnorm, seed = 1,
                printfun = printfun)
identical(res, res.seq)
# Example with worker initialization
mean <- 20
sd <- 10
myfun <- function(r) rdnorm(r, mean = mean, sd = sd)</pre>
res <- unlist(performParallel(p, rep(1000, 100), fun = myfun, seed = 123,
```

snowFT-rand 7

```
initexpr = library(extraDistr), export = c("mean", "sd")))
hist(res)

# See example in ?snowFT for plotting cluster usage.

## End(Not run)
```

snowFT-rand

Random Number Generation

Description

Initialize independent random number streams to be used in the cluster. It uses the L'Ecuyer's random number generator implemented in the **rlecuyer** package.

Usage

```
clusterSetupRNG.FT (cl, type = "RNGstream", streamper="replicate", ...)
clusterSetupRNGstreamRepli (cl, seed=rep(12345,6), n, ...)
```

Arguments

cl	Cluster object.
type	Type of the RNG. Currently, only "RNGstream" is supported. It initializes the L'Ecuyer's RNG.
streamper	Mode of the initialization. Value "node" initializes one random number stream per node. Value "replicate" initializes one stream per replicate.
	Arguments passed to the underlying function (see details bellow).
seed	A single integer or a vector of six integer values used as seed for the RNG.
n	Number of streams to be created. It should correspond to the number of replicates in the computation.

Details

clusterSetupRNG.FT calls one of the following functions, while passing arguments (cl, ...): For streamper="node", the snow function clusterSetupRNGstream is called; For streamper="replicate", the function clusterSetupRNGstreamRepli is called. In the latter case, the argument n has to be given that corresponds to the total number of streams created for the computation. This mode is used by clusterApplyFT. Note that when using the function performParallel, the user does not need to initialize the RNG separately, since it is accomplished within the function.

clusterSetupRNGstreamRepli loads the **rlecuyer** package and on each node it creates n streams. The streams are named by their ordinal number.

8 snowFT-startstop

Examples

```
## Not run:
# Generate 50 independent (normally distributed) random numbers
# on 3 nodes using 10 RNG streams
cl <- makeClusterFT(3)</pre>
r < -10
# reproducible results
for (i in 1:3) {
    clusterSetupRNG.FT(cl, streamper = "replicate", n = r, seed = 123)
    cat("\n")
    print(unlist(clusterApplyFT(cl, rep(5,r), rnorm, gentype = "RNGstream")[[1]]))
}
# non-reproducible results (method used in snow)
for (i in 1:3) {
    clusterSetupRNG.FT(cl, streamper = "node", seed = 123)
    cat("\n")
   print(unlist(clusterApplyFT(cl, rep(5,r), rnorm, gentype = "RNGstream")[[1]]))
}
stopClusterFT(cl)
## End(Not run)
```

snowFT-startstop

Starting snowFT Cluster

Description

Functions to start and stop a snowFT cluster and to set default cluster options.

Usage

Arguments

	C1 .	
spec	Cluster	\$17e

type Character string that specifies cluster type. "MPI" and "SOCK" are supported

("PVM" is currently not available).

names Used only for the 'SOCK' layer. It should be a vector of host names, or a list

containing specification for each host (see Example in makeCluster). Due to the dynamic resizing feature, the length of this vector (or list) does not need to match the size of the cluster spec - it is used as a pool from which hosts are taken as they are needed. If names is NULL, each node is started on 'localhost'.

snowFT-startstop 9

ft_verbose	If TRUE, debugging messages are sent to standard output.
• • •	Cluster option specifications. A useful option is outfile, specifying name of a file to which slave node output is to be directed.
cl	Cluster object.

Details

makeClusterFT starts a cluster of the specified or default type, loads the **snowFT** library on each node and returns a reference to the cluster. See makeCluster for more details. stopClusterFT stops the cluster.

See Also

snow-startstop functions of the snow package.

Examples

```
## Not run:
cl <- makeClusterFT(5, ft_verbose = TRUE)
res <- clusterApplyFT(cl, 1:10, get("+"), y = 3)
stopClusterFT(res[[2]])
print(unlist(res[[1]]))
## End(Not run)</pre>
```

Index

```
*Topic package
    snowFT-package, 2
*Topic programming
    snowFT-cluster, 3
    snowFT-package, 2
    snowFT-rand, 7
    snowFT-startstop, 8
clusterApplyFT, 7
{\tt clusterApplyFT} \ ({\tt snowFT-cluster}), \ 3
clusterCall, 3, 4
clusterCallpart (snowFT-cluster), 3
clusterEvalQ, 4
clusterEvalQpart (snowFT-cluster), 3
clusterSetupRNG.FT, 5
clusterSetupRNG.FT (snowFT-rand), 7
clusterSetupRNGstream, 7
clusterSetupRNGstreamRepli
        (snowFT-rand), 7
makeCluster, 5, 8, 9
makeClusterFT, 4, 5
makeClusterFT (snowFT-startstop), 8
makeSOCKclusterFT (snowFT-startstop), 8
performParallel, 2, 3, 7
performParallel(snowFT-cluster), 3
printClusterInfo(snowFT-cluster), 3
snowFT (snowFT-package), 2
snowFT-cluster, 3
snowFT-package, 2
snowFT-rand, 7
snowFT-startstop, 8
stopClusterFT (snowFT-startstop), 8
```