Package 'diagonals'

May 8, 2021

Title Block Diagonal Extraction or Replacement

Version 6.0.0

Description Several tools for handling block-matrix diagonals and similar constructs are implemented. Block-diagonal matrices can be extracted or removed using two small functions implemented here. In addition, non-square matrices are supported. Block diagonal matrices occur when two dimensions of a data set are combined along one edge of a matrix. For example, trade-flow data in the 'decompr' and 'gvc' packages have each country-industry combination occur along both edges of the matrix.
Depends R (>= 2.10)
License GPL-3
<pre>URL https://qua.st/diagonals, https://github.com/bquast/diagonals</pre>
BugReports https://github.com/bquast/diagonals/issues
Suggests testthat, knitr, rmarkdown
VignetteBuilder knitr
RoxygenNote 7.1.1
Encoding UTF-8
NeedsCompilation no
Author Bastiaan Quast [aut, cre]
Maintainer Bastiaan Quast dquast@gmail.com>
Repository CRAN
Date/Publication 2021-05-08 16:20:02 UTC
R topics documented:
diagonals
fatdiag
split_vector
Index 4

2 fatdiag

|--|

Description

Several tools for handling block-matrix diagonals and similar constructs are implemented. Block-diagonal matrices can be extracted or removed using two small functions implemented here. In addition, non-square matrices are supported. Block diagonal matrices occur when two dimensions of a data set are combined along one edge of a matrix. For example, trade-flow data in the decompr' and 'gvc' packages have each country-industry combination occur along both edges of the matrix.

Author(s)

Bastiaan Quast

degmail.com>

See Also

https://qua.st/diagonals

fatdiag	Fat Matrix Diagonals

Description

```
Fat Matrix Diagonals fatdiag set
```

Usage

```
fatdiag(x = 1, steps = NULL, size = NULL, nrow = NULL, ncol = NULL) fatdiag(x, steps = NULL, size = NULL, on\_diagonal = TRUE) <- value
```

Arguments

X	a matrix where the dimensions are integer multiples of size or integer dividors of steps
steps	the required number of steps (block matrices) across the diagonal
size	the width or height of the matrix being dropped over the diagonal of matrix x
nrow	the number of rows
ncol	the number of columns
on_diagonal	should the operation be applied to the elements on the fat diagonal.
value	replacement value

split_vector 3

Details

Either steps or size is expected to be provided.

Functions

• fatdiag<-: the set version of fatdiag

Examples

```
fatdiag(12, steps=3)

( m <- matrix(111, nrow=6, ncol=9) )
fatdiag(m, steps=3) <- 5

fatdiag(m, steps=3)

fatdiag(12, size=4)

fatdiag(12, size=c(3,4) )</pre>
```

split_vector

Split Vector

Description

Split Vector

Usage

```
split_vector(x, steps = NULL, size = NULL, replacement = 0)
```

Arguments

x a numeric or character vector

steps the number of steps size the size of the step

replacement value to be inserted on the diagonal, by default this is zero (0).

Details

Either steps or size is expected to be provided.

Index

```
diagonals, 2
fatdiag, 2
fatdiag<- (fatdiag), 2
split_vector, 3</pre>
```